

gconfmm

2.28.3

Generated by Doxygen 1.9.8



<b>1 gconfmm Reference Manual</b>	<b>1</b>
1.1 Description	1
1.2 Basic Usage	1
<b>2 Topic Index</b>	<b>3</b>
2.1 Topics	3
<b>3 Namespace Index</b>	<b>5</b>
3.1 Namespace List	5
<b>4 Hierarchical Index</b>	<b>7</b>
4.1 Class Hierarchy	7
<b>5 Class Index</b>	<b>9</b>
5.1 Class List	9
<b>6 Topic Documentation</b>	<b>11</b>
6.1 gconfmm Enums and Flags	11
6.1.1 Detailed Description	11
6.1.2 Enumeration Type Documentation	11
6.1.2.1 ClientErrorHandlingMode	11
6.1.2.2 ClientPreloadType	12
6.1.2.3 UnsetFlags	12
6.1.2.4 ValueType	12
<b>7 Namespace Documentation</b>	<b>13</b>
7.1 Glib Namespace Reference	13
7.2 Gnome Namespace Reference	13
7.3 Gnome::Conf Namespace Reference	13
7.3.1 Typedef Documentation	14
7.3.1.1 Callback	14
7.3.1.2 ValuePair	14
7.3.1.3 ValueTypePair	14
7.3.2 Function Documentation	14
7.3.2.1 init()	14
<b>8 Class Documentation</b>	<b>15</b>
8.1 Gnome::Conf::ChangeSet Class Reference	15
8.1.1 Detailed Description	17
8.1.2 Member Typedef Documentation	17
8.1.2.1 ForeachSlot	17
8.1.3 Constructor & Destructor Documentation	17
8.1.3.1 ChangeSet() [1/3]	17
8.1.3.2 ChangeSet() [2/3]	17
8.1.3.3 ChangeSet() [3/3]	17

8.1.3.4 ~ChangeSet()	17
8.1.4 Member Function Documentation	17
8.1.4.1 clear()	17
8.1.4.2 exists()	18
8.1.4.3 for_each()	18
8.1.4.4 gobj() [1/2]	18
8.1.4.5 gobj() [2/2]	18
8.1.4.6 gobj_copy()	18
8.1.4.7 operator=()	18
8.1.4.8 remove()	18
8.1.4.9 set() [1/6]	19
8.1.4.10 set() [2/6]	19
8.1.4.11 set() [3/6]	19
8.1.4.12 set() [4/6]	19
8.1.4.13 set() [5/6]	19
8.1.4.14 set() [6/6]	19
8.1.4.15 size()	20
8.1.4.16 unset()	20
8.1.5 Member Data Documentation	20
8.1.5.1 gobject_	20
8.2 Gnome::Conf::Client Class Reference	20
8.2.1 Detailed Description	24
8.2.2 Member Typedef Documentation	24
8.2.2.1 SListHandleBools	24
8.2.2.2 SListHandleFloats	24
8.2.2.3 SListHandleInts	24
8.2.3 Constructor & Destructor Documentation	24
8.2.3.1 ~Client()	24
8.2.4 Member Function Documentation	24
8.2.4.1 add_dir()	24
8.2.4.2 all_dirs()	25
8.2.4.3 all_entries()	25
8.2.4.4 change_set_commit()	26
8.2.4.5 change_set_from_current()	26
8.2.4.6 change_set_reverse()	27
8.2.4.7 clear_cache()	27
8.2.4.8 dir_exists()	27
8.2.4.9 error()	28
8.2.4.10 get()	28
8.2.4.11 get_bool()	28
8.2.4.12 get_bool_list()	28
8.2.4.13 get_client_for_engine()	28

8.2.4.14 <code>get_default_client()</code> . . . . .	29
8.2.4.15 <code>get_default_from_schema()</code> . . . . .	29
8.2.4.16 <code>get_entry()</code> [1/2] . . . . .	29
8.2.4.17 <code>get_entry()</code> [2/2] . . . . .	30
8.2.4.18 <code>get_float()</code> . . . . .	30
8.2.4.19 <code>get_float_list()</code> . . . . .	30
8.2.4.20 <code>get_int()</code> . . . . .	31
8.2.4.21 <code>get_int_list()</code> . . . . .	31
8.2.4.22 <code>get_pair()</code> . . . . .	31
8.2.4.23 <code>get_schema()</code> . . . . .	32
8.2.4.24 <code>get_schema_list()</code> . . . . .	32
8.2.4.25 <code>get_string()</code> . . . . .	32
8.2.4.26 <code>get_string_list()</code> . . . . .	32
8.2.4.27 <code>get_without_default()</code> . . . . .	32
8.2.4.28 <code>gobj()</code> [1/2] . . . . .	33
8.2.4.29 <code>gobj()</code> [2/2] . . . . .	33
8.2.4.30 <code>gobj_copy()</code> . . . . .	33
8.2.4.31 <code>key_is_writable()</code> . . . . .	33
8.2.4.32 <code>notify()</code> . . . . .	34
8.2.4.33 <code>notify_add()</code> . . . . .	34
8.2.4.34 <code>notify_remove()</code> . . . . .	34
8.2.4.35 <code>on_error()</code> . . . . .	35
8.2.4.36 <code>on_unreturned_error()</code> . . . . .	35
8.2.4.37 <code>on_value_changed()</code> . . . . .	35
8.2.4.38 <code>preload()</code> . . . . .	35
8.2.4.39 <code>recursive_unset()</code> . . . . .	35
8.2.4.40 <code>remove_dir()</code> . . . . .	36
8.2.4.41 <code>set()</code> [1/6] . . . . .	36
8.2.4.42 <code>set()</code> [2/6] . . . . .	36
8.2.4.43 <code>set()</code> [3/6] . . . . .	37
8.2.4.44 <code>set()</code> [4/6] . . . . .	37
8.2.4.45 <code>set()</code> [5/6] . . . . .	38
8.2.4.46 <code>set()</code> [6/6] . . . . .	38
8.2.4.47 <code>set_bool_list()</code> . . . . .	39
8.2.4.48 <code>set_error_handling()</code> . . . . .	39
8.2.4.49 <code>set_float_list()</code> . . . . .	39
8.2.4.50 <code>set_int_list()</code> . . . . .	39
8.2.4.51 <code>set_schema_list()</code> . . . . .	39
8.2.4.52 <code>set_string_list()</code> . . . . .	39
8.2.4.53 <code>signal_error()</code> . . . . .	39
8.2.4.54 <code>signal_value_changed()</code> . . . . .	40
8.2.4.55 <code>suggest_sync()</code> . . . . .	40

8.2.4.56 unset()	40
8.2.4.57 value_changed()	40
8.2.5 Friends And Related Symbol Documentation	41
8.2.5.1 wrap()	41
8.3 Gnome::Conf::Entry Class Reference	41
8.3.1 Detailed Description	42
8.3.2 Constructor & Destructor Documentation	42
8.3.2.1 Entry() [1/4]	42
8.3.2.2 Entry() [2/4]	43
8.3.2.3 Entry() [3/4]	43
8.3.2.4 ~Entry()	43
8.3.2.5 Entry() [4/4]	43
8.3.3 Member Function Documentation	43
8.3.3.1 get_is_default()	43
8.3.3.2 get_is_writable()	43
8.3.3.3 get_key()	43
8.3.3.4 get_schema_name()	43
8.3.3.5 get_value()	44
8.3.3.6 gobj() [1/2]	44
8.3.3.7 gobj() [2/2]	44
8.3.3.8 gobj_copy()	44
8.3.3.9 operator=()	44
8.3.3.10 set_is_default()	44
8.3.3.11 set_is_writable()	44
8.3.3.12 set_schema_name()	45
8.3.3.13 set_value()	45
8.3.4 Member Data Documentation	45
8.3.4.1 gobject_	45
8.4 Gnome::Conf::Error Class Reference	45
8.4.1 Detailed Description	46
8.4.2 Member Enumeration Documentation	46
8.4.2.1 Code	46
8.4.3 Constructor & Destructor Documentation	47
8.4.3.1 Error() [1/2]	47
8.4.3.2 Error() [2/2]	47
8.4.4 Member Function Documentation	47
8.4.4.1 code()	47
8.5 Gnome::Conf::Schema Class Reference	48
8.5.1 Constructor & Destructor Documentation	49
8.5.1.1 Schema() [1/3]	49
8.5.1.2 Schema() [2/3]	49
8.5.1.3 Schema() [3/3]	49

8.5.1.4 ~Schema()	49
8.5.2 Member Function Documentation	49
8.5.2.1 get_car_type()	49
8.5.2.2 get_cdr_type()	49
8.5.2.3 get_default_value()	50
8.5.2.4 get_list_type()	50
8.5.2.5 get_locale()	50
8.5.2.6 get_long_desc()	50
8.5.2.7 get_owner()	50
8.5.2.8 get_short_desc()	50
8.5.2.9 get_type()	50
8.5.2.10 gobj() [1/2]	50
8.5.2.11 gobj() [2/2]	50
8.5.2.12 gobj_copy()	50
8.5.2.13 operator=()	51
8.5.2.14 set_car_type()	51
8.5.2.15 set_cdr_type()	51
8.5.2.16 set_default_value()	51
8.5.2.17 set_list_type()	51
8.5.2.18 set_locale()	51
8.5.2.19 set_long_desc()	51
8.5.2.20 set_owner()	51
8.5.2.21 set_short_desc()	51
8.5.2.22 set_type()	52
8.5.3 Friends And Related Symbol Documentation	52
8.5.3.1 wrap()	52
8.5.4 Member Data Documentation	52
8.5.4.1 gobject_	52
8.6 Gnome::Conf::SetInterface Class Reference	52
8.6.1 Detailed Description	53
8.6.2 Member Function Documentation	53
8.6.2.1 set() [1/7]	53
8.6.2.2 set() [2/7]	54
8.6.2.3 set() [3/7]	54
8.6.2.4 set() [4/7]	54
8.6.2.5 set() [5/7]	54
8.6.2.6 set() [6/7]	54
8.6.2.7 set() [7/7]	54
8.6.2.8 set_bool_list()	55
8.6.2.9 set_float_list()	55
8.6.2.10 set_int_list()	55
8.6.2.11 set_schema_list()	55

8.6.2.12 set_string_list()	55
8.7 Gnome::Conf::Value Class Reference	55
8.7.1 Detailed Description	57
8.7.2 Constructor & Destructor Documentation	58
8.7.2.1 Value() [1/3]	58
8.7.2.2 Value() [2/3]	58
8.7.2.3 ~Value()	58
8.7.2.4 Value() [3/3]	58
8.7.3 Member Function Documentation	58
8.7.3.1 get_bool()	58
8.7.3.2 get_bool_list()	58
8.7.3.3 get_car()	59
8.7.3.4 get_cdr()	59
8.7.3.5 get_float()	59
8.7.3.6 get_float_list()	59
8.7.3.7 get_int()	59
8.7.3.8 get_int_list()	59
8.7.3.9 get_list_type()	60
8.7.3.10 get_schema()	60
8.7.3.11 get_schema_list()	60
8.7.3.12 get_string()	60
8.7.3.13 get_string_list()	60
8.7.3.14 get_type()	60
8.7.3.15 gobj() [1/2]	61
8.7.3.16 gobj() [2/2]	61
8.7.3.17 gobj_copy()	61
8.7.3.18 operator=()	61
8.7.3.19 set() [1/5]	61
8.7.3.20 set() [2/5]	61
8.7.3.21 set() [3/5]	61
8.7.3.22 set() [4/5]	61
8.7.3.23 set() [5/5]	62
8.7.3.24 set_bool_list()	62
8.7.3.25 set_car()	62
8.7.3.26 set_cdr()	62
8.7.3.27 set_float_list()	62
8.7.3.28 set_int_list()	62
8.7.3.29 set_list_type()	63
8.7.3.30 set_schema_list()	63
8.7.3.31 set_string_list()	63
8.7.3.32 to_string()	63
8.7.4 Friends And Related Symbol Documentation	63



---

8.7.4.1 wrap()	63
8.7.5 Member Data Documentation	64
8.7.5.1 gobject_	64
<b>Index</b>	<b>65</b>



# Chapter 1

## gconfmm Reference Manual

### 1.1 Description

gconfmm is the official C++ interface for the GConf client API for storing and retrieving configuration data. See [Gnome::Conf::Client](#).

### 1.2 Basic Usage

Include the gconfmm header:

```
#include <gconfmm.h>
```

(You may include individual headers, such as `gconfmm/client.h` instead.)

If your source file is `program.cc`, you can compile it with:

```
g++ program.cc -o program `pkg-config --cflags --libs gconfmm-2.6`
```

Alternatively, if using `autoconf`, use the following in `configure.ac`:

```
PKG_CHECK_MODULES([GCONFMM], [gconfmm-2.4])
```

Then use the generated `GCONFMM_CFLAGS` and `GCONFMM_LIBS` variables in the project `Makefile.am` files. For example:

```
program_CPPFLAGS = $(GCONFMM_CFLAGS)
program_LDADD = $(GCONFMM_LIBS)
```



## Chapter 2

# Topic Index

### 2.1 Topics

Here is a list of all topics with brief descriptions:

gconfmm Enums and Flags . . . . .	<a href="#">11</a>
-----------------------------------	--------------------



## Chapter 3

# Namespace Index

### 3.1 Namespace List

Here is a list of all namespaces with brief descriptions:

<a href="#">Glib</a>	.....	<a href="#">13</a>
<a href="#">Gnome</a>	.....	<a href="#">13</a>
<a href="#">Gnome::Conf</a>	.....	<a href="#">13</a>





## Chapter 4

# Hierarchical Index

### 4.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

Glib::Error	
Gnome::Conf::Error . . . . .	<a href="#">45</a>
Glib::Object	
Gnome::Conf::Client . . . . .	<a href="#">20</a>
Gnome::Conf::Entry . . . . .	<a href="#">41</a>
Gnome::Conf::Schema . . . . .	<a href="#">48</a>
Gnome::Conf::SetInterface . . . . .	<a href="#">52</a>
Gnome::Conf::ChangeSet . . . . .	<a href="#">15</a>
Gnome::Conf::Client . . . . .	<a href="#">20</a>
Gnome::Conf::Value . . . . .	<a href="#">55</a>



# Chapter 5

## Class Index

### 5.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

<a href="#">Gnome::Conf::ChangeSet</a>	
A <a href="#">ChangeSet</a> is a set of changes to the GConf database that can be committed and reversed easily . . . . .	15
<a href="#">Gnome::Conf::Client</a>	
The main <a href="#">Gnome::Conf</a> object . . . . .	20
<a href="#">Gnome::Conf::Entry</a>	
An <a href="#">Entry</a> stores an entry from a GConf "directory", including a key-value pair, the name of the <a href="#">Schema</a> applicable to this entry, whether the value is a default value, and whether GConf can write a new value at this key . . . . .	41
<a href="#">Gnome::Conf::Error</a>	
Exception class for <a href="#">Gnome::Conf::Client</a> errors . . . . .	45
<a href="#">Gnome::Conf::Schema</a> . . . . .	48
<a href="#">Gnome::Conf::SetInterface</a>	
Common Interface for key-value settable objects . . . . .	52
<a href="#">Gnome::Conf::Value</a>	
Wrapper for primitive types . . . . .	55



# Chapter 6

## Topic Documentation

### 6.1 gconfmm Enums and Flags

#### Enumerations

- enum `Gnome::Conf::ClientErrorHandlingMode` {  
    `Gnome::Conf::CLIENT_HANDLE_NONE` ,  
    `Gnome::Conf::CLIENT_HANDLE_UNRETURNED` ,  
    `Gnome::Conf::CLIENT_HANDLE_ALL` }
- enum `Gnome::Conf::ClientPreloadType` {  
    `Gnome::Conf::CLIENT_PRELOAD_NONE` ,  
    `Gnome::Conf::CLIENT_PRELOAD_ONELEVEL` ,  
    `Gnome::Conf::CLIENT_PRELOAD_RECURSIVE` }
- enum `Gnome::Conf::ValueType` {  
    `Gnome::Conf::VALUE_INVALID` ,  
    `Gnome::Conf::VALUE_STRING` ,  
    `Gnome::Conf::VALUE_INT` ,  
    `Gnome::Conf::VALUE_FLOAT` ,  
    `Gnome::Conf::VALUE_BOOL` ,  
    `Gnome::Conf::VALUE_SCHEMA` ,  
    `Gnome::Conf::VALUE_LIST` ,  
    `Gnome::Conf::VALUE_PAIR` }
- enum `Gnome::Conf::UnsetFlags` { `Gnome::Conf::UNSET_INCLUDING_SCHEMA_NAMES` }

#### 6.1.1 Detailed Description

#### 6.1.2 Enumeration Type Documentation

##### 6.1.2.1 ClientErrorHandlingMode

```
enum Gnome::Conf::ClientErrorHandlingMode
```

#### Enumerator

CLIENT_HANDLE_NONE	
CLIENT_HANDLE_UNRETURNED	
CLIENT_HANDLE_ALL	

### 6.1.2.2 ClientPreloadType

```
enum Gnome::Conf::ClientPreloadType
```

Enumerator

CLIENT_PRELOAD_NONE	
CLIENT_PRELOAD_ONELEVEL	
CLIENT_PRELOAD_RECURSIVE	

### 6.1.2.3 UnsetFlags

```
enum Gnome::Conf::UnsetFlags
```

Enumerator

UNSET_INCLUDING_SCHEMA_NAMES	
------------------------------	--

### 6.1.2.4 ValueType

```
enum Gnome::Conf::ValueType
```

Enumerator

VALUE_INVALID	
VALUE_STRING	
VALUE_INT	
VALUE_FLOAT	
VALUE_BOOL	
VALUE_SCHEMA	
VALUE_LIST	
VALUE_PAIR	

# Chapter 7

## Namespace Documentation

### 7.1 Glib Namespace Reference

### 7.2 Gnome Namespace Reference

#### Namespaces

- namespace [Conf](#)

### 7.3 Gnome::Conf Namespace Reference

#### Classes

- class [ChangeSet](#)  
*A [ChangeSet](#) is a set of changes to the GConf database that can be committed and reversed easily.*
- class [Client](#)  
*The main [Gnome::Conf](#) object.*
- class [Entry](#)  
*An [Entry](#) stores an entry from a GConf "directory", including a key-value pair, the name of the [Schema](#) applicable to this entry, whether the value is a default value, and whether GConf can write a new value at this key.*
- class [Error](#)  
*Exception class for [Gnome::Conf::Client](#) errors.*
- class [Schema](#)
- class [SetInterface](#)  
*Common Interface for key-value settable objects.*
- class [Value](#)  
*Wrapper for primitive types.*

#### Typedefs

- typedef `std::pair< Value, Value >` [ValuePair](#)
- typedef `std::pair< ValueType, ValueType >` [ValueTypePair](#)
- typedef `sigc::slot< void, guint, Entry >` [Callback](#)

## Enumerations

- enum `ClientErrorHandlingMode` {  
`CLIENT_HANDLE_NONE` ,  
`CLIENT_HANDLE_UNRETURNED` ,  
`CLIENT_HANDLE_ALL` }
- enum `ClientPreloadType` {  
`CLIENT_PRELOAD_NONE` ,  
`CLIENT_PRELOAD_ONELEVEL` ,  
`CLIENT_PRELOAD_RECURSIVE` }
- enum `ValueType` {  
`VALUE_INVALID` ,  
`VALUE_STRING` ,  
`VALUE_INT` ,  
`VALUE_FLOAT` ,  
`VALUE_BOOL` ,  
`VALUE_SCHEMA` ,  
`VALUE_LIST` ,  
`VALUE_PAIR` }
- enum `UnsetFlags` { `UNSET_INCLUDING_SCHEMA_NAMES` }

## Functions

- void `init` ()

## 7.3.1 Typedef Documentation

### 7.3.1.1 Callback

```
typedef sigc::slot<void, guint, Entry> Gnome::Conf::Callback
```

### 7.3.1.2 ValuePair

```
typedef std::pair<Value, Value> Gnome::Conf::ValuePair
```

### 7.3.1.3 ValueTypePair

```
typedef std::pair<ValueType, ValueType> Gnome::Conf::ValueTypePair
```

## 7.3.2 Function Documentation

### 7.3.2.1 init()

```
void Gnome::Conf::init ( )
```



## Chapter 8


# Class Documentation

### 8.1 Gnome::Conf::ChangeSet Class Reference


A [ChangeSet](#) is a set of changes to the GConf database that can be committed and reversed easily.

```
#include <gconfmm/changeset.h>
```

Inheritance diagram for Gnome::Conf::ChangeSet:



Collaboration diagram for Gnome::Conf::ChangeSet:



## Public Types

- typedef sigc::slot< void, const Glib::ustring &, const [Value](#) & > [ForeachSlot](#)

## Public Member Functions

- [ChangeSet](#) ()
- [ChangeSet](#) (GConfChangeSet \*castitem, bool make\_a\_copy=false)
- [ChangeSet](#) (const [ChangeSet](#) &src)
- [ChangeSet](#) & [operator=](#) (const [ChangeSet](#) &src)
- virtual [~ChangeSet](#) ()
- GConfChangeSet \* [gobj](#) ()
- const GConfChangeSet \* [gobj](#) () const
- GConfChangeSet \* [gobj\\_copy](#) () const
- void [clear](#) ()  
*Clear all entries.*
- unsigned int [size](#) () const  
*Returns the number of keys in the changeset.*
- void [remove](#) (const Glib::ustring &key)  
*Remove the specified key from the changeset.*
- [Value](#) \* [exists](#) (const Glib::ustring &key) const  
*Check whether the given key will be modified by a commit operation.*
- void [unset](#) (const Glib::ustring &key)  
*Unset the given key.*
- virtual void [set](#) (const Glib::ustring &key, const [Value](#) &value)
- virtual void [set](#) (const Glib::ustring &key, bool what)
- virtual void [set](#) (const Glib::ustring &key, int what)
- virtual void [set](#) (const Glib::ustring &key, double what)
- virtual void [set](#) (const Glib::ustring &key, const Glib::ustring &what)
- virtual void [set](#) (const Glib::ustring &key, const [Schema](#) &what)
- void [for\\_each](#) (const [ForeachSlot](#) &slot)  
*Iterate over the keys marked in this [ChangeSet](#).*

## Public Member Functions inherited from [Gnome::Conf::SetInterface](#)

- void [set](#) (const Glib::ustring &key, const [ValuePair](#) &pair)
- void [set\\_int\\_list](#) (const Glib::ustring &key, const SListHandle\_ValueInt &list)
- void [set\\_bool\\_list](#) (const Glib::ustring &key, const SListHandle\_ValueBool &list)
- void [set\\_float\\_list](#) (const Glib::ustring &key, const SListHandle\_ValueFloat &list)
- void [set\\_string\\_list](#) (const Glib::ustring &key, const SListHandle\_ValueString &list)
- void [set\\_schema\\_list](#) (const Glib::ustring &key, const SListHandle\_ValueSchema &list)

## Protected Attributes

- GConfChangeSet \* [gobject\\_](#)

### 8.1.1 Detailed Description

A [ChangeSet](#) is a set of changes to the GConf database that can be committed and reversed easily.

The changes can be both set and unset operations. Currently the [ChangeSet](#) operations are not atomic, and not specially optimized for. However, it is suitable for use, for instance, preferences dialogs.

The `set*()` methods do not throw errors, they simply store the keys and the values.

See also

[Client::change\\_set\\_from\\_current\(\)](#), [Client::change\\_set\\_commit\(\)](#), [Client::change\\_set\\_reverse\(\)](#).

### 8.1.2 Member Typedef Documentation

#### 8.1.2.1 ForeachSlot

```
typedef sigc::slot<void, const Glib::ustring&, const Value&> Gnome::Conf::ChangeSet::ForeachSlot
```

### 8.1.3 Constructor & Destructor Documentation

#### 8.1.3.1 ChangeSet() [1/3]

```
Gnome::Conf::ChangeSet::ChangeSet ( )
```

#### 8.1.3.2 ChangeSet() [2/3]

```
Gnome::Conf::ChangeSet::ChangeSet (
    GConfChangeSet * castitem,
    bool make_a_copy = false ) [explicit]
```

#### 8.1.3.3 ChangeSet() [3/3]

```
Gnome::Conf::ChangeSet::ChangeSet (
    const ChangeSet & src )
```

#### 8.1.3.4 ~ChangeSet()

```
virtual Gnome::Conf::ChangeSet::~~ChangeSet ( ) [virtual]
```

### 8.1.4 Member Function Documentation

#### 8.1.4.1 clear()

```
void Gnome::Conf::ChangeSet::clear ( )
```

Clear all entries.

After this method, committing the changeset is a no-op.

#### 8.1.4.2 exists()

```
Value * Gnome::Conf::ChangeSet::exists (
    const Glib::ustring & key ) const
```

Check whether the given key will be modified by a commit operation.

##### Returns

0 if the key will not be modified, else the modified value. Remember to delete the [Value](#).

#### 8.1.4.3 for\_each()

```
void Gnome::Conf::ChangeSet::for_each (
    const ForeachSlot & slot )
```

Iterate over the keys marked in this [ChangeSet](#).

Calls `slot` for each key-value pair that is marked in the [ChangeSet](#). Keys marked unset will have a [Value](#) with type `VALUE_INVALID`.

#### 8.1.4.4 gobj() [1/2]

```
GConfChangeSet * Gnome::Conf::ChangeSet::gobj ( ) [inline]
```

#### 8.1.4.5 gobj() [2/2]

```
const GConfChangeSet * Gnome::Conf::ChangeSet::gobj ( ) const [inline]
```

#### 8.1.4.6 gobj\_copy()

```
GConfChangeSet * Gnome::Conf::ChangeSet::gobj_copy ( ) const
```

#### 8.1.4.7 operator=()

```
ChangeSet & Gnome::Conf::ChangeSet::operator= (
    const ChangeSet & src )
```

#### 8.1.4.8 remove()

```
void Gnome::Conf::ChangeSet::remove (
    const Glib::ustring & key )
```

Remove the specified key from the changeset.

This means that the given key will not be modified by a commit.

**8.1.4.9 set()** [1/6]

```
virtual void Gnome::Conf::ChangeSet::set (
    const Glib::ustring & key,
    bool what ) [virtual]
```

Implements [Gnome::Conf::SetInterface](#).

**8.1.4.10 set()** [2/6]

```
virtual void Gnome::Conf::ChangeSet::set (
    const Glib::ustring & key,
    const Glib::ustring & what ) [virtual]
```

Implements [Gnome::Conf::SetInterface](#).

**8.1.4.11 set()** [3/6]

```
virtual void Gnome::Conf::ChangeSet::set (
    const Glib::ustring & key,
    const Schema & what ) [virtual]
```

Implements [Gnome::Conf::SetInterface](#).

**8.1.4.12 set()** [4/6]

```
virtual void Gnome::Conf::ChangeSet::set (
    const Glib::ustring & key,
    const Value & value ) [virtual]
```

Implements [Gnome::Conf::SetInterface](#).

**8.1.4.13 set()** [5/6]

```
virtual void Gnome::Conf::ChangeSet::set (
    const Glib::ustring & key,
    double what ) [virtual]
```

Implements [Gnome::Conf::SetInterface](#).

**8.1.4.14 set()** [6/6]

```
virtual void Gnome::Conf::ChangeSet::set (
    const Glib::ustring & key,
    int what ) [virtual]
```

Implements [Gnome::Conf::SetInterface](#).

#### 8.1.4.15 size()

```
unsigned int Gnome::Conf::ChangeSet::size ( ) const
```

Returns the number of keys in the changeset.

#### 8.1.4.16 unset()

```
void Gnome::Conf::ChangeSet::unset (
    const Glib::ustring & key )
```

Unset the given key.

Mark the key, so that it will be removed from the configuration database during a commit.

### 8.1.5 Member Data Documentation

#### 8.1.5.1 gobject\_

```
GConfChangeSet* Gnome::Conf::ChangeSet::gobject_ [protected]
```

The documentation for this class was generated from the following file:


- gconfmm/changeset.h

## 8.2 Gnome::Conf::Client Class Reference


The main [Gnome::Conf](#) object.

```
#include <gconfmm/client.h>
```

Inheritance diagram for Gnome::Conf::Client:



Collaboration diagram for Gnome::Conf::Client:



## Public Types

- typedef Glib::SListHandle< int, BasicTypeTraits< int > > [SListHandleInts](#)
- typedef Glib::SListHandle< bool, BasicTypeTraits< bool > > [SListHandleBools](#)
- typedef Glib::SListHandle< double, BasicTypeTraits< double > > [SListHandleFloats](#)

## Public Member Functions

- virtual [~Client](#) ()
- GConfClient \* [gobj](#) ()
  - Provides access to the underlying C GObject.*
- const GConfClient \* [gobj](#) () const
  - Provides access to the underlying C GObject.*
- GConfClient \* [gobj\\_copy](#) ()
  - Provides access to the underlying C instance. The caller is responsible for unrefing it. Use when directly setting fields in structs.*
- void [add\\_dir](#) (const Glib::ustring &dir, [ClientPreloadType](#) preload=CLIENT\_PRELOAD\_NONE)
  - Add a directory to the list of directories the [Client](#) will watch.*
- void [remove\\_dir](#) (const Glib::ustring &dir)
  - Remove a directory from the list of directories the [Client](#) will watch.*
- guint [notify\\_add](#) (const Glib::ustring &namespace\_section, [Callback](#) callback)
  - Request notification of changes to namespace\_section.*
- void [notify\\_remove](#) (guint cnxn)
  - Cancel a notification request.*
- void [notify](#) (const Glib::ustring &key)
  - Emits the value\_changed signal and notifies listeners as if key had been changed.*
- void [set\\_error\\_handling](#) ([ClientErrorHandlingMode](#) mode)
- void [clear\\_cache](#) ()
  - Clear the client-side cache.*
- void [preload](#) (const Glib::ustring &dirname, [ClientPreloadType](#) type)
  - Preloads a directory.*
- [Value get](#) (const Glib::ustring &key) const
  - Get the value of a configuration key.*
- [Value get\\_without\\_default](#) (const Glib::ustring &key) const
  - Get the value of a configuration key, without falling back to the default if the key has not been set.*

- [Value get\\_default\\_from\\_schema](#) (const Glib::ustring &key) const  
*Get the default value of this key by looking it up in the appropriate schema.*
- [Entry get\\_entry](#) (const Glib::ustring &key, bool use\_schema\_default=true) const  
*Get the complete [Entry](#) of the specified key.*
- [Entry get\\_entry](#) (const Glib::ustring &key, const char \*locale, bool use\_schema\_default=true) const  
*Get the complete [Entry](#) of the specified key.*
- void [unset](#) (const Glib::ustring &key)  
*Unset a configuration key.*
- void [recursive\\_unset](#) (const Glib::ustring &key, [UnsetFlags](#) flags=UNSET\_INCLUDING\_SCHEMA\_NAMES)  
*Unsets all keys below key, including key itself.*
- Glib::SListHandle< [Entry](#) > [all\\_entries](#) (const Glib::ustring &dir) const  
*Retrieve all keys in the given configuration directory.*
- Glib::SListHandle< Glib::ustring > [all\\_dirs](#) (const Glib::ustring &dir) const  
*Retrieve all subdirectories of a given configuration directory.*
- void [suggest\\_sync](#) ()  
*Suggest to the GConf server that a sync of cached data to stable storage would be appropriate now.*
- bool [dir\\_exists](#) (const Glib::ustring &p1) const  
*Determine whether a given configuration directory exists.*
- bool [key\\_is\\_writable](#) (const Glib::ustring &p1) const  
*Determine whether a given configuration key is writeable by the application.*
- double [get\\_float](#) (const Glib::ustring &key) const  
*Get the float value at the given configuration key.*
- gint [get\\_int](#) (const Glib::ustring &key) const  
*Get the integer at the given configuration key.*
- bool [get\\_bool](#) (const Glib::ustring &key) const  
*Get the boolean at the given configuration key.*
- Glib::ustring [get\\_string](#) (const Glib::ustring &key) const  
*Get the string at the given configuration key.*
- [Schema get\\_schema](#) (const Glib::ustring &key) const  
*Get the [Schema](#) at the given configuration key.*
- SListHandle\_ValueInt [get\\_int\\_list](#) (const Glib::ustring &key) const  
*Get the list of integers at the given configuration key.*
- SListHandle\_ValueBool [get\\_bool\\_list](#) (const Glib::ustring &key) const  
*Get the list of booleans at the given configuration key.*
- SListHandle\_ValueFloat [get\\_float\\_list](#) (const Glib::ustring &key) const  
*Get the list of doubles at the given configuration key.*
- SListHandle\_ValueSchema [get\\_schema\\_list](#) (const Glib::ustring &key) const  
*Get the list of Schemas at the given configuration key.*
- SListHandle\_ValueString [get\\_string\\_list](#) (const Glib::ustring &key) const  
*Get the list of strings at the given configuration key.*
- [ValuePair get\\_pair](#) (const Glib::ustring &key, [ValueTypePair](#) types) const  
*Get the pair at the given configuration key.*
- void [set](#) (const Glib::ustring &key, int what)  
*Set the given configuration key to the specified integer value.*
- void [set](#) (const Glib::ustring &key, bool what)  
*Set the given configuration key to the specified boolean value.*
- void [set](#) (const Glib::ustring &key, double what)  
*Set the given configuration key to the specified double value.*
- void [set](#) (const Glib::ustring &key, const Glib::ustring &what)  
*Set the given configuration key to the specified string.*
- void [set](#) (const Glib::ustring &key, const [Schema](#) &what)



Set the given configuration key to the specified *Schema*.

- void `set` (const Glib::ustring &key, const *Value* &what)
- Set the given configuration key to the specified *Value*.
- void `set_int_list` (const Glib::ustring &key, const *SListHandleInts* &what)
- void `set_bool_list` (const Glib::ustring &key, const *SListHandleBools* &what)
- void `set_float_list` (const Glib::ustring &key, const *SListHandleFloats* &what)
- void `set_schema_list` (const Glib::ustring &key, const Glib::SListHandle< *Schema* > &what)
- void `set_string_list` (const Glib::ustring &key, const Glib::SListHandle< Glib::ustring > &what)
- *ChangeSet* `change_set_from_current` (const Glib::SArray &set)

Create a *ChangeSet* from the current values of the configuration database.

- void `change_set_commit` (*ChangeSet* &set, bool remove\_committed)

Commit the *ChangeSet* to the configuration database.

- *ChangeSet* `change_set_reverse` (const *ChangeSet* &set)

Creates a *ChangeSet* to reverse the effects of the given *ChangeSet*.

- Glib::SignalProxy2< void, const Glib::ustring &, const *Value* & > `signal_value_changed` ()

A signal emitted when a value changes.

- void `value_changed` (const Glib::ustring &key, const *Value* &value)
- Glib::SignalProxy1< void, const Glib::Error & > `signal_error` ()

A signal emitted when an error occurs.

- void `error` (const Glib::Error &error)

## Public Member Functions inherited from Gnome::Conf::SetInterface

- void `set` (const Glib::ustring &key, const *ValuePair* &pair)
- void `set_int_list` (const Glib::ustring &key, const *SListHandle\_ValueInt* &list)
- void `set_bool_list` (const Glib::ustring &key, const *SListHandle\_ValueBool* &list)
- void `set_float_list` (const Glib::ustring &key, const *SListHandle\_ValueFloat* &list)
- void `set_string_list` (const Glib::ustring &key, const *SListHandle\_ValueString* &list)
- void `set_schema_list` (const Glib::ustring &key, const *SListHandle\_ValueSchema* &list)

## Static Public Member Functions

- static Glib::RefPtr< *Client* > `get_default_client` ()
- Get the default client object for this application.
- static Glib::RefPtr< *Client* > `get_client_for_engine` (GConfEngine \*engine)

## Protected Member Functions

- virtual void `on_value_changed` (const Glib::ustring &key, const *Value* &value)
- virtual void `on_unreturned_error` (const Glib::Error &error)
- virtual void `on_error` (const Glib::Error &error)

## Related Symbols

(Note that these are not member symbols.)

- Glib::RefPtr< *Gnome::Conf::Client* > `wrap` (GConfClient \*object, bool take\_copy=false)
- A *Glib::wrap()* method for this object.

## 8.2.1 Detailed Description

The main [Gnome::Conf](#) object.

This class allows you to interface with the [Gnome](#) configuration system. Generally, it stores key-value pairs. The keys have an hierarchical namespace, with elements separated by slashes. The values are either typed primitives (int, bool, string, float or a [Schema](#)), or lists of primitives or pairs of primitives (for limits on the compound values, see [Value](#)). For conventions on the names of keys, see the GConf documentation.

## 8.2.2 Member Typedef Documentation

### 8.2.2.1 SListHandleBools

```
typedef Glib::SListHandle< bool, BasicTypeTraits<bool> > Gnome::Conf::Client::SListHandleBools
```

### 8.2.2.2 SListHandleFloats

```
typedef Glib::SListHandle< double, BasicTypeTraits<double> > Gnome::Conf::Client::SListHandleFloats
```

### 8.2.2.3 SListHandleInts

```
typedef Glib::SListHandle< int, BasicTypeTraits<int> > Gnome::Conf::Client::SListHandleInts
```

## 8.2.3 Constructor & Destructor Documentation

### 8.2.3.1 ~Client()

```
virtual Gnome::Conf::Client::~~Client ( ) [virtual]
```

## 8.2.4 Member Function Documentation

### 8.2.4.1 add\_dir()

```
void Gnome::Conf::Client::add\_dir (
    const Glib::ustring & dir,
    ClientPreloadType preload = CLIENT\_PRELOAD\_NONE )
```

Add a directory to the list of directories the [Client](#) will watch.

Any changes to keys below this directory will cause the "value\_changed" signal to be emitted. When you add the directory, you can request that the [Client](#) preloads its contents - see [ClientPreloadType](#) for details.

Added directories may not overlap. That is, if you add "/foo", you may not add "/foo/bar". However you can add "/foo" and "/bar". You can also add "/foo" multiple times; if you add a directory multiple times, it will not be removed until you call [remove\\_dir\(\)](#) an equal number of times.

## Parameters

<i>dir</i>	the directory to watch.
<i>preload</i>	the preload type (if any) to be performed.

**8.2.4.2 all\_dirs()**

```
Glib::SListHandle< Glib::ustring > Gnome::Conf::Client::all_dirs (
    const Glib::ustring & dir ) const
```

Retrieve all subdirectories of a given configuration directory.

## Parameters

<i>dir</i>	the configuration directory to scan.
------------	--------------------------------------

## Returns

a container with the names of the subdirectories.

## Exceptions

<i>Gnome::Conf::Error.</i>	
----------------------------	--

**8.2.4.3 all\_entries()**

```
Glib::SListHandle< Entry > Gnome::Conf::Client::all_entries (
    const Glib::ustring & dir ) const
```

Retrieve all keys in the given configuration directory.

Get all the configuration keys in the given directory, without recursion.

## Parameters

<i>dir</i>	the configuration directory to scan.
------------	--------------------------------------

## Returns

a container with the names of the configuration keys.

## Exceptions

<i>Gnome::Conf::Error.</i>	
----------------------------	--

#### 8.2.4.4 change\_set\_commit()

```
void Gnome::Conf::Client::change_set_commit (
    ChangeSet & set,
    bool remove_committed )
```

Commit the [ChangeSet](#) to the configuration database.

Commits the configuration changes in the [ChangeSet](#) to the database. If `remove_committed` is `true`, all successfully committed keys will be removed from the [ChangeSet](#). If an error occurs, a [Gnome::Conf::Error](#) will be thrown. This operation is not atomic - an error will be thrown on the first error.

##### Parameters

<i>set</i>	the <a href="#">ChangeSet</a> to commit.
<i>remove_committed</i>	whether to remove successfully-committed keys from the <a href="#">ChangeSet</a> .

##### Exceptions

<a href="#">Gnome::Conf::Error</a>	
------------------------------------	--

##### See also

[ChangeSet](#)

#### 8.2.4.5 change\_set\_from\_current()

```
ChangeSet Gnome::Conf::Client::change_set_from_current (
    const Glib::SArray & set )
```

Create a [ChangeSet](#) from the current values of the configuration database.

Creates a [ChangeSet](#) containing the current values of all the keys listed in the `set`. For instance, this could be used in a preferences dialog as an undo operation.

##### Parameters

<i>set</i>	A container of the configuration keys to backup.
------------	--

##### Returns

the [ChangeSet](#) with the current values.

##### Exceptions

<a href="#">Gnome::Conf::Error</a>	
------------------------------------	--

See also

[ChangeSet](#)

#### 8.2.4.6 change\_set\_reverse()

```
ChangeSet Gnome::Conf::Client::change_set_reverse (
    const ChangeSet & set )
```

Creates a [ChangeSet](#) to reverse the effects of the given [ChangeSet](#).

Creates a [ChangeSet](#) that contains the current values of the keys in `set`, effectively creating a back-up of the values in the database that will be modified when the `set` will be committed. For instance, this allows you to create a back-up changeset to use in case of errors, or an undo facility for preferences.

##### Parameters

<code>set</code>	the <a href="#">ChangeSet</a> to reverse.
------------------	---

##### Returns

the reverse [ChangeSet](#).

##### Exceptions

<a href="#">Gnome::Conf::Error</a>	
------------------------------------	--

See also

[ChangeSet](#)

#### 8.2.4.7 clear\_cache()

```
void Gnome::Conf::Client::clear_cache ( )
```

Clear the client-side cache.

#### 8.2.4.8 dir\_exists()

```
bool Gnome::Conf::Client::dir_exists (
    const Glib::ustring & p1 ) const
```

Determine whether a given configuration directory exists.

##### Returns

true if the directory exists.

### Exceptions

<i>Gnome::Conf::Error.</i>	
----------------------------	--

#### 8.2.4.9 error()

```
void Gnome::Conf::Client::error (
    const Glib::Error & error )
```

#### 8.2.4.10 get()

```
Value Gnome::Conf::Client::get (
    const Glib::ustring & key ) const
```

Get the value of a configuration key.

@parameter key: the configuration key to retrieve.

### Returns

the [Value](#) of the key.

### Exceptions

<i>Gnome::Conf::Error.</i>	
----------------------------	--

#### 8.2.4.11 get\_bool()

```
bool Gnome::Conf::Client::get_bool (
    const Glib::ustring & key ) const
```

Get the boolean at the given configuration key.

#### 8.2.4.12 get\_bool\_list()

```
SListHandle_ValueBool Gnome::Conf::Client::get_bool_list (
    const Glib::ustring & key ) const
```

Get the list of booleans at the given configuration key.

#### 8.2.4.13 get\_client\_for\_engine()

```
static Glib::RefPtr< Client > Gnome::Conf::Client::get_client_for_engine (
    GConfEngine * engine ) [static]
```

#### 8.2.4.14 get\_default\_client()

```
static Glib::RefPtr< Client > Gnome::Conf::Client::get_default_client ( ) [static]
```

Get the default client object for this application.

The object is a Singleton, so you will always get the same instance. Most applications should use this.

#### 8.2.4.15 get\_default\_from\_schema()

```
Value Gnome::Conf::Client::get_default_from_schema (
    const Glib::ustring & key ) const
```

Get the default value of this key by looking it up in the appropriate schema.

@parameter key: the configuration key to retrieve.

##### Returns

the default [Value](#) of the key.

##### Exceptions

<i>Gnome::Conf::Error.</i>	
----------------------------	--

#### 8.2.4.16 get\_entry() [1/2]

```
Entry Gnome::Conf::Client::get_entry (
    const Glib::ustring & key,
    bool use_schema_default = true ) const
```

Get the complete [Entry](#) of the specified key.

Uses the default locale

##### Parameters

<i>key</i>	the configuration key to retrieve.
<i>use_schema_default</i>	whether to fall back to the <a href="#">Schema</a> default value if the specified configuration key has not been set.

##### Returns

an [Entry](#) for the corresponding configuration key.

##### Exceptions

<i>Gnome::Conf::Error.</i>	
----------------------------	--

#### 8.2.4.17 `get_entry()` [2/2]

```
Entry Gnome::Conf::Client::get_entry (
    const Glib::ustring & key,
    const char * locale,
    bool use_schema_default = true ) const
```

Get the complete [Entry](#) of the specified key.

##### Parameters

<i>key</i>	the configuration key to retrieve.
<i>locale</i>	the locale for the user-visible strings in the <a href="#">Entry</a> 's <a href="#">Schema</a> . Use 0 to use the default.
<i>use_schema_default</i>	whether to fall back to the <a href="#">Schema</a> default value if the specified configuration key has not been set.

##### Returns

an [Entry](#) for the corresponding configuration key.

##### Exceptions

<a href="#">Gnome::Conf::Error</a> .	
--------------------------------------	--

#### 8.2.4.18 `get_float()`

```
double Gnome::Conf::Client::get_float (
    const Glib::ustring & key ) const
```

Get the float value at the given configuration key.

Throws an error if the key does not contain the appropriate type.

##### Parameters

<i>key</i>	the configuration key to fetch.
------------	---------------------------------

##### Returns

the value at the specified configuration key.

##### Exceptions

<a href="#">Gnome::Conf::Error</a>	
------------------------------------	--

#### 8.2.4.19 `get_float_list()`

```
SListHandle_ValueFloat Gnome::Conf::Client::get_float_list (
```



```
const Glib::ustring & key ) const
```

Get the list of doubles at the given configuration key.

#### 8.2.4.20 get\_int()

```
gint Gnome::Conf::Client::get_int (
    const Glib::ustring & key ) const
```

Get the integer at the given configuration key.

#### 8.2.4.21 get\_int\_list()

```
SListHandle_ValueInt Gnome::Conf::Client::get_int_list (
    const Glib::ustring & key ) const
```

Get the list of integers at the given configuration key.

If the given key is not a list, or the list elements are not of the appropriate type, an error will be thrown.

##### Parameters

<i>key</i>	the configuration key that contains the list.
------------	---

##### Returns

a Glib::SListHandle of the appropriate type.

##### Exceptions

<a href="#">Gnome::Conf::Error</a>	
------------------------------------	--

#### 8.2.4.22 get\_pair()

```
ValuePair Gnome::Conf::Client::get_pair (
    const Glib::ustring & key,
    ValueTypePair types ) const
```

Get the pair at the given configuration key.

The pair's elements must have the types given in `types` respectively. If the value is not a pair or the types do not match, an error will be thrown.

##### Parameters

<i>key</i>	the configuration key that contains the pair.
<i>types</i>	a pair of the expected types of the values.

**Returns**

a ValuePair.

**Exceptions**

<a href="#">Gnome::Conf::Error</a>	
------------------------------------	--

**8.2.4.23 get\_schema()**

```
Schema Gnome::Conf::Client::get_schema (
    const Glib::ustring & key ) const
```

Get the [Schema](#) at the given configuration key.

**8.2.4.24 get\_schema\_list()**

```
SListHandle_ValueSchema Gnome::Conf::Client::get_schema_list (
    const Glib::ustring & key ) const
```

Get the list of Schemas at the given configuration key.

**8.2.4.25 get\_string()**

```
Glib::ustring Gnome::Conf::Client::get_string (
    const Glib::ustring & key ) const
```

Get the string at the given configuration key.

**8.2.4.26 get\_string\_list()**

```
SListHandle_ValueString Gnome::Conf::Client::get_string_list (
    const Glib::ustring & key ) const
```

Get the list of strings at the given configuration key.

**8.2.4.27 get\_without\_default()**

```
Value Gnome::Conf::Client::get_without_default (
    const Glib::ustring & key ) const
```

Get the value of a configuration key, without falling back to the default if the key has not been set.

In that case, the type of the value will be VALUE\_INVALID.

## Parameters

<i>key</i>	the configuration key to retrieve.
------------	------------------------------------

## Returns

the [Value](#) of the key.

## Exceptions

<i>Gnome::Conf::Error.</i>	
----------------------------	--

**8.2.4.28 gobj()** [1/2]

```
GConfClient * Gnome::Conf::Client::gobj ( ) [inline]
```

Provides access to the underlying C GObject.

**8.2.4.29 gobj()** [2/2]

```
const GConfClient * Gnome::Conf::Client::gobj ( ) const [inline]
```

Provides access to the underlying C GObject.

**8.2.4.30 gobj\_copy()**

```
GConfClient * Gnome::Conf::Client::gobj_copy ( )
```

Provides access to the underlying C instance. The caller is responsible for unrefing it. Use when directly setting fields in structs.

**8.2.4.31 key\_is\_writable()**

```
bool Gnome::Conf::Client::key_is_writable (
    const Glib::ustring & p1 ) const
```

Determine whether a given configuration key is writeable by the application.

## Returns

true if the key is writeable.

## Exceptions

<i>Gnome::Conf::Error.</i>	
----------------------------	--

#### 8.2.4.32 notify()

```
void Gnome::Conf::Client::notify (
    const Glib::ustring & key )
```

Emits the `value_changed` signal and notifies listeners as if `key` had been changed.

##### Parameters

<i>key</i>	The key that has changed.
------------	---------------------------

@newin2p24

#### 8.2.4.33 notify\_add()

```
guint Gnome::Conf::Client::notify_add (
    const Glib::ustring & namespace_section,
    Callback callback )
```

Request notification of changes to `namespace_section`.

This includes the key `namespace_section` itself, and any keys below it. For the notification to happen, `namespace_section` must be equal to or below one of the directories added with [add\\_dir\(\)](#). You can still call [notify\\_add\(\)](#) for other directories, but no notification will be received until you add a directory above or equal to `namespace_section`. One implication of this is that [remove\\_dir\(\)](#) temporarily disables notifications that were below the removed directory.

The callback will be called with the key that changed and the [Entry](#) that holds the new [Value](#). If the [Value](#) has a type of `VALUE_INVALID`, then the key has been unset.

The function returns a connection ID you can use when calling [notify\\_remove\(\)](#).

##### Parameters

<i>namespace_section</i>	the namespace section for which notification is required.
<i>callback</i>	the sigc::slot to call when the a key under <code>namespace_section</code> changes.

##### Returns

a connection id that can be passed to [notify\\_remove\(\)](#) to cancel the notification request.

#### 8.2.4.34 notify\_remove()

```
void Gnome::Conf::Client::notify_remove (
    guint cnxn )
```

Cancel a notification request.

## Parameters

<i>cnxn</i>	a connection id, previously returned by <a href="#">notify_add()</a>
-------------	--

## See also

[notify\\_add\(\)](#)**8.2.4.35 on\_error()**

```
virtual void Gnome::Conf::Client::on_error (
    const Glib::Error & error ) [protected], [virtual]
```

**8.2.4.36 on\_unreturned\_error()**

```
virtual void Gnome::Conf::Client::on_unreturned_error (
    const Glib::Error & error ) [protected], [virtual]
```

**8.2.4.37 on\_value\_changed()**

```
virtual void Gnome::Conf::Client::on_value_changed (
    const Glib::ustring & key,
    const Value & value ) [protected], [virtual]
```

**8.2.4.38 preload()**

```
void Gnome::Conf::Client::preload (
    const Glib::ustring & dirname,
    ClientPreloadType type )
```

Preloads a directory.

Normally this happens automatically with [add\\_dir\(\)](#), but if you've called [clear\\_cache\(\)](#) you may need to do it again.

## See also

[add\\_dir\(\)](#)**8.2.4.39 recursive\_unset()**

```
void Gnome::Conf::Client::recursive_unset (
    const Glib::ustring & key,
    UnsetFlags flags = UNSET_INCLUDING_SCHEMA_NAMES )
```

Unsets all keys below *key*, including *key* itself.

If any unset fails, it continues on to unset as much as it can. The first failure is then thrown as an exception.

## Parameters

<i>key</i>	The configuration key to unset.
<i>flags</i>	Change how the unset is done.

## Exceptions

<a href="#"><i>Gnome::Conf::Error</i></a>	
---	--

@newin2p24

#### 8.2.4.40 remove\_dir()

```
void Gnome::Conf::Client::remove_dir (
    const Glib::ustring & dir )
```

Remove a directory from the list of directories the [Client](#) will watch.

## See also

[add\\_dir\(\)](#)

#### 8.2.4.41 set() [1/6]

```
void Gnome::Conf::Client::set (
    const Glib::ustring & key,
    bool what ) [virtual]
```

Set the given configuration key to the specified boolean value.

Set the given configuration key to the specified integer value.

## Parameters

<i>key</i>	the configuration key to set.
<i>what</i>	the value to set it to.

## Exceptions

<a href="#"><i>Gnome::Conf::Error</i></a>	
---	--

Implements [Gnome::Conf::SetInterface](#).

#### 8.2.4.42 set() [2/6]

```
void Gnome::Conf::Client::set (
    const Glib::ustring & key,
    const Glib::ustring & what ) [virtual]
```

Set the given configuration key to the specified string.

Set the given configuration key to the specified integer value.

#### Parameters

<i>key</i>	the configuration key to set.
<i>what</i>	the value to set it to.

#### Exceptions

<a href="#">Gnome::Conf::Error</a>	
------------------------------------	--

Implements [Gnome::Conf::SetInterface](#).

#### 8.2.4.43 set() [3/6]

```
void Gnome::Conf::Client::set (  
    const Glib::ustring & key,  
    const Schema & what ) [virtual]
```

Set the given configuration key to the specified [Schema](#).

Set the given configuration key to the specified integer value.

#### Parameters

<i>key</i>	the configuration key to set.
<i>what</i>	the value to set it to.

#### Exceptions

<a href="#">Gnome::Conf::Error</a>	
------------------------------------	--

Implements [Gnome::Conf::SetInterface](#).

#### 8.2.4.44 set() [4/6]

```
void Gnome::Conf::Client::set (  
    const Glib::ustring & key,  
    const Value & what ) [virtual]
```

Set the given configuration key to the specified [Value](#).

Set the given configuration key to the specified integer value.

#### Parameters

<i>key</i>	the configuration key to set.
<i>what</i>	the value to set it to.

## Exceptions

<a href="#">Gnome::Conf::Error</a>	
------------------------------------	--

Implements [Gnome::Conf::SetInterface](#).

**8.2.4.45 set()** [5/6]

```
void Gnome::Conf::Client::set (  
    const Glib::ustring & key,  
    double what ) [virtual]
```

Set the given configuration key to the specified double value.

Set the given configuration key to the specified integer value.

## Parameters

<i>key</i>	the configuration key to set.
<i>what</i>	the value to set it to.

## Exceptions

<a href="#">Gnome::Conf::Error</a>	
------------------------------------	--

Implements [Gnome::Conf::SetInterface](#).

**8.2.4.46 set()** [6/6]

```
void Gnome::Conf::Client::set (  
    const Glib::ustring & key,  
    int what ) [virtual]
```

Set the given configuration key to the specified integer value.

## Parameters

<i>key</i>	the configuration key to set.
<i>what</i>	the value to set it to.

## Exceptions

<a href="#">Gnome::Conf::Error</a>	
------------------------------------	--

Implements [Gnome::Conf::SetInterface](#).



#### 8.2.4.47 set\_bool\_list()

```
void Gnome::Conf::Client::set_bool_list (
    const Glib::ustring & key,
    const SListHandleBools & what )
```

#### 8.2.4.48 set\_error\_handling()

```
void Gnome::Conf::Client::set_error_handling (
    ClientErrorHandlingMode mode )
```

#### 8.2.4.49 set\_float\_list()

```
void Gnome::Conf::Client::set_float_list (
    const Glib::ustring & key,
    const SListHandleFloats & what )
```

#### 8.2.4.50 set\_int\_list()

```
void Gnome::Conf::Client::set_int_list (
    const Glib::ustring & key,
    const SListHandleInts & what )
```

#### 8.2.4.51 set\_schema\_list()

```
void Gnome::Conf::Client::set_schema_list (
    const Glib::ustring & key,
    const Glib::SListHandle< Schema > & what )
```

#### 8.2.4.52 set\_string\_list()

```
void Gnome::Conf::Client::set_string_list (
    const Glib::ustring & key,
    const Glib::SListHandle< Glib::ustring > & what )
```

#### 8.2.4.53 signal\_error()

```
Glib::SignalProxy1< void, const Glib::Error & > Gnome::Conf::Client::signal_error ( )
```

A signal emitted when an error occurs.

This signal will be emitted when an error occurs, right before the throw() of the error.

#### Prototype:

```
void on_my_error(const Glib::Error& error)
```

#### 8.2.4.54 signal\_value\_changed()

```
Glib::SignalProxy2< void, const Glib::ustring &, const Value & > Gnome::Conf::Client::signal↔
_value_changed ( )
```

A signal emitted when a value changes.

This signal will only be called for directories added with [add\\_dir\(\)](#).

##### Prototype:

```
void on_my_value_changed(const Glib::ustring& key, const Value& value)
```

#### 8.2.4.55 suggest\_sync()

```
void Gnome::Conf::Client::suggest_sync ( )
```

Suggest to the GConf server that a sync of cached data to stable storage would be appropriate now.

##### Exceptions

<i>Gnome::Conf::Error.</i>	
----------------------------	--

#### 8.2.4.56 unset()

```
void Gnome::Conf::Client::unset (
    const Glib::ustring & key )
```

Unset a configuration key.

##### Parameters

<i>key</i>	the configuration key to unset.
------------	---------------------------------

##### Exceptions

<i>Gnome::Conf::Error.</i>	
----------------------------	--

#### 8.2.4.57 value\_changed()

```
void Gnome::Conf::Client::value_changed (
    const Glib::ustring & key,
    const Value & value )
```

## 8.2.5 Friends And Related Symbol Documentation

### 8.2.5.1 wrap()

```
Glib::RefPtr< Gnome::Conf::Client > wrap (
    GConfClient * object,
    bool take_copy = false ) [related]
```

A Glib::wrap() method for this object.

#### Parameters

<i>object</i>	The C instance.
<i>take_copy</i>	False if the result should take ownership of the C instance. True if it should take a new copy or ref.

#### Returns

A C++ instance that wraps this C instance.

The documentation for this class was generated from the following file:


- gconfmm/client.h

## 8.3 Gnome::Conf::Entry Class Reference

An [Entry](#) stores an entry from a GConf "directory", including a key-value pair, the name of the [Schema](#) applicable to this entry, whether the value is a default value, and whether GConf can write a new value at this key.

```
#include <gconfmm/entry.h>
```

Collaboration diagram for Gnome::Conf::Entry:



## Public Member Functions

- [Entry](#) ()
  - [Entry](#) (GConfEntry \*castitem, bool make\_a\_copy=false)
  - [Entry](#) (const [Entry](#) &src)
  - [Entry](#) & operator= (const [Entry](#) &src)
  - ~[Entry](#) ()
  - GConfEntry \* [gobj](#) ()
  - const GConfEntry \* [gobj](#) () const
  - GConfEntry \* [gobj\\_copy](#) () const
- Provides access to the underlying C instance. The caller is responsible for freeing it. Use when directly setting fields in structs.*
- [Entry](#) (const Glib::ustring &key, const [Value](#) &value)
- Construct an [Entry](#) with the given *key* and *value*.*
- void [set\\_value](#) (const [Value](#) &val)
- Set the [Value](#) of the entry.*
- void [set\\_schema\\_name](#) (const Glib::ustring &val)
- Set the [Schema](#) name of the entry.*
- void [set\\_is\\_default](#) (bool is\_default=true)
- Set whether the value has originated from the default given in the [Schema](#).*
- void [set\\_is\\_writable](#) (bool is\_writable=true)
- Set whether the given configuration key is writeable.*
- [Value](#) [get\\_value](#) () const
- Retrieve the value of the entry.*
- Glib::ustring [get\\_schema\\_name](#) () const
- Retrieve the [Schema](#) name associated with the given entry.*
- Glib::ustring [get\\_key](#) () const
  - bool [get\\_is\\_default](#) () const
  - bool [get\\_is\\_writable](#) () const

## Protected Attributes

- GConfEntry \* [gobject\\_](#)

## 8.3.1 Detailed Description

An [Entry](#) stores an entry from a GConf "directory", including a key-value pair, the name of the [Schema](#) applicable to this entry, whether the value is a default value, and whether GConf can write a new value at this key.

The key should be an absolute key, not a relative key.

## 8.3.2 Constructor & Destructor Documentation

### 8.3.2.1 Entry() [1/4]

```
Gnome::Conf::Entry::Entry ( )
```

### 8.3.2.2 Entry() [2/4]

```
Gnome::Conf::Entry::Entry (
    GConfEntry * castitem,
    bool make_a_copy = false ) [explicit]
```

### 8.3.2.3 Entry() [3/4]

```
Gnome::Conf::Entry::Entry (
    const Entry & src )
```

### 8.3.2.4 ~Entry()

```
Gnome::Conf::Entry::~Entry ( )
```

### 8.3.2.5 Entry() [4/4]

```
Gnome::Conf::Entry::Entry (
    const Glib::ustring & key,
    const Value & value )
```

Construct an [Entry](#) with the given key and value.

## 8.3.3 Member Function Documentation

### 8.3.3.1 get\_is\_default()

```
bool Gnome::Conf::Entry::get_is_default ( ) const
```

### 8.3.3.2 get\_is\_writable()

```
bool Gnome::Conf::Entry::get_is_writable ( ) const
```

### 8.3.3.3 get\_key()

```
Glib::ustring Gnome::Conf::Entry::get_key ( ) const
```

### 8.3.3.4 get\_schema\_name()

```
Glib::ustring Gnome::Conf::Entry::get_schema_name ( ) const
```

Retrieve the [Schema](#) name associated with the given entry.

### 8.3.3.5 get\_value()

```
Value Gnome::Conf::Entry::get_value ( ) const
```

Retrieve the value of the entry.

#### Returns

a copy the entry's value.

### 8.3.3.6 gobj() [1/2]

```
GConfEntry * Gnome::Conf::Entry::gobj ( ) [inline]
```

### 8.3.3.7 gobj() [2/2]

```
const GConfEntry * Gnome::Conf::Entry::gobj ( ) const [inline]
```

### 8.3.3.8 gobj\_copy()

```
GConfEntry * Gnome::Conf::Entry::gobj_copy ( ) const
```

Provides access to the underlying C instance. The caller is responsible for freeing it. Use when directly setting fields in structs.

### 8.3.3.9 operator=()

```
Entry & Gnome::Conf::Entry::operator= (
    const Entry & src )
```

### 8.3.3.10 set\_is\_default()

```
void Gnome::Conf::Entry::set_is_default (
    bool is_default = true )
```

Set whether the value has originated from the default given in the [Schema](#).

### 8.3.3.11 set\_is\_writable()

```
void Gnome::Conf::Entry::set_is_writable (
    bool is_writable = true )
```

Set whether the given configuration key is writeable.

### 8.3.3.12 set\_schema\_name()

```
void Gnome::Conf::Entry::set_schema_name (
    const Glib::ustring & val )
```

Set the [Schema](#) name of the entry.

### 8.3.3.13 set\_value()

```
void Gnome::Conf::Entry::set_value (
    const Value & val )
```

Set the [Value](#) of the entry.

## 8.3.4 Member Data Documentation

### 8.3.4.1 gobject\_

```
GConfEntry* Gnome::Conf::Entry::gobject_ [protected]
```

The documentation for this class was generated from the following file:


- gconfmm/entry.h

## 8.4 Gnome::Conf::Error Class Reference


Exception class for [Gnome::Conf::Client](#) errors.

```
#include <gconfmm/client.h>
```

Inheritance diagram for Gnome::Conf::Error:



Collaboration diagram for Gnome::Conf::Error:



### Public Types

- enum `Code` {  
    `SUCCESS` = 0 ,  
    `NO_SERVER` = 2 ,  
    `NO_PERMISSION` = 3 ,  
    `BAD_ADDRESS` = 4 ,  
    `PARSE_ERROR` = 6 ,  
    `CORRUPT` = 7 ,  
    `TYPE_MISMATCH` = 8 ,  
    `IS_DIR` = 9 ,  
    `IS_KEY` = 10 ,  
    `OVERRIDDEN` = 11 ,  
    `OAF_ERROR` = 12 ,  
    `LOCAL_ENGINE` = 13 ,  
    `LOCK_FAILED` = 14 ,  
    `NO_WRITABLE_DATABASE` = 15 ,  
    `IN_SHUTDOWN` = 16 }

### Public Member Functions

- `Error` (`Code` error\_code, const `Glib::ustring` &error\_message)
- `Error` (`GError` \*gobject)
- `Code` code () const

## 8.4.1 Detailed Description

Exception class for `Gnome::Conf::Client` errors.

## 8.4.2 Member Enumeration Documentation

### 8.4.2.1 Code

```
enum Gnome::Conf::Error::Code
```



## Enumerator

SUCCESS	
NO_SERVER	
NO_PERMISSION	
BAD_ADDRESS	
PARSE_ERROR	
CORRUPT	
TYPE_MISMATCH	
IS_DIR	
IS_KEY	
OVERRIDDEN	
OAF_ERROR	
LOCAL_ENGINE	
LOCK_FAILED	
NO_WRITABLE_DATABASE	
IN_SHUTDOWN	

### 8.4.3 Constructor & Destructor Documentation

#### 8.4.3.1 Error() [1/2]

```
Gnome::Conf::Error::Error (
    Code error_code,
    const Glib::ustring & error_message )
```

#### 8.4.3.2 Error() [2/2]

```
Gnome::Conf::Error::Error (
    GError * gobject ) [explicit]
```

### 8.4.4 Member Function Documentation

#### 8.4.4.1 code()

```
Code Gnome::Conf::Error::code ( ) const
```


The documentation for this class was generated from the following file:

- gconfmm/client.h

## 8.5 Gnome::Conf::Schema Class Reference

```
#include <gconfmm/schema.h>
```

Collaboration diagram for Gnome::Conf::Schema:



### Public Member Functions

- [Schema](#) ()
- [Schema](#) (GConfSchema \*castitem, bool make\_a\_copy=false)
- [Schema](#) (const [Schema](#) &src)
- [Schema](#) & [operator=](#) (const [Schema](#) &src)
- [~Schema](#) ()
- GConfSchema \* [gobj](#) ()
- const GConfSchema \* [gobj](#) () const
- GConfSchema \* [gobj\\_copy](#) () const

*Provides access to the underlying C instance. The caller is responsible for freeing it. Use when directly setting fields in structs.*

- void [set\\_type](#) (ValueType type)
- void [set\\_list\\_type](#) (ValueType type)
- void [set\\_car\\_type](#) (ValueType type)
- void [set\\_cdr\\_type](#) (ValueType type)
- void [set\\_locale](#) (const **std::string** &locale)
- void [set\\_short\\_desc](#) (const Glib::ustring &desc)
- void [set\\_long\\_desc](#) (const Glib::ustring &desc)
- void [set\\_owner](#) (const Glib::ustring &owner)
- void [set\\_default\\_value](#) (const [Value](#) &value)
- [ValueType](#) [get\\_type](#) () const
- [ValueType](#) [get\\_list\\_type](#) () const
- [ValueType](#) [get\\_car\\_type](#) () const
- [ValueType](#) [get\\_cdr\\_type](#) () const
- **std::string** [get\\_locale](#) () const
- Glib::ustring [get\\_short\\_desc](#) () const
- Glib::ustring [get\\_long\\_desc](#) () const
- Glib::ustring [get\\_owner](#) () const
- [Value](#) [get\\_default\\_value](#) () const

## Protected Attributes

- GConfSchema \* [gobject\\_](#)

## Related Symbols

(Note that these are not member symbols.)

- [Gnome::Conf::Schema wrap](#) (GConfSchema \*object, bool take\_copy=false)  
A *Glib::wrap()* method for this object.

## 8.5.1 Constructor & Destructor Documentation

### 8.5.1.1 Schema() [1/3]

```
Gnome::Conf::Schema::Schema ( )
```

### 8.5.1.2 Schema() [2/3]

```
Gnome::Conf::Schema::Schema (
    GConfSchema * castitem,
    bool make_a_copy = false ) [explicit]
```

### 8.5.1.3 Schema() [3/3]

```
Gnome::Conf::Schema::Schema (
    const Schema & src )
```

### 8.5.1.4 ~Schema()

```
Gnome::Conf::Schema::~Schema ( )
```

## 8.5.2 Member Function Documentation

### 8.5.2.1 get\_car\_type()

```
ValueType Gnome::Conf::Schema::get_car_type ( ) const
```

### 8.5.2.2 get\_cdr\_type()

```
ValueType Gnome::Conf::Schema::get_cdr_type ( ) const
```

### 8.5.2.3 get\_default\_value()

`Value` `Gnome::Conf::Schema::get_default_value ( ) const`

### 8.5.2.4 get\_list\_type()

`ValueType` `Gnome::Conf::Schema::get_list_type ( ) const`

### 8.5.2.5 get\_locale()

`std::string` `Gnome::Conf::Schema::get_locale ( ) const`

### 8.5.2.6 get\_long\_desc()

`Glib::ustring` `Gnome::Conf::Schema::get_long_desc ( ) const`

### 8.5.2.7 get\_owner()

`Glib::ustring` `Gnome::Conf::Schema::get_owner ( ) const`

### 8.5.2.8 get\_short\_desc()

`Glib::ustring` `Gnome::Conf::Schema::get_short_desc ( ) const`

### 8.5.2.9 get\_type()

`ValueType` `Gnome::Conf::Schema::get_type ( ) const`

### 8.5.2.10 gobj() [1/2]

`GConfSchema *` `Gnome::Conf::Schema::gobj ( ) [inline]`

### 8.5.2.11 gobj() [2/2]

`const GConfSchema *` `Gnome::Conf::Schema::gobj ( ) const [inline]`

### 8.5.2.12 gobj\_copy()

`GConfSchema *` `Gnome::Conf::Schema::gobj_copy ( ) const`

Provides access to the underlying C instance. The caller is responsible for freeing it. Use when directly setting fields in structs.

#### 8.5.2.13 operator=()

```
Schema & Gnome::Conf::Schema::operator= (
    const Schema & src )
```

#### 8.5.2.14 set\_car\_type()

```
void Gnome::Conf::Schema::set_car_type (
    ValueType type )
```

#### 8.5.2.15 set\_cdr\_type()

```
void Gnome::Conf::Schema::set_cdr_type (
    ValueType type )
```

#### 8.5.2.16 set\_default\_value()

```
void Gnome::Conf::Schema::set_default_value (
    const Value & value )
```

#### 8.5.2.17 set\_list\_type()

```
void Gnome::Conf::Schema::set_list_type (
    ValueType type )
```

#### 8.5.2.18 set\_locale()

```
void Gnome::Conf::Schema::set_locale (
    const std::string & locale )
```

#### 8.5.2.19 set\_long\_desc()

```
void Gnome::Conf::Schema::set_long_desc (
    const Glib::ustring & desc )
```

#### 8.5.2.20 set\_owner()

```
void Gnome::Conf::Schema::set_owner (
    const Glib::ustring & owner )
```

#### 8.5.2.21 set\_short\_desc()

```
void Gnome::Conf::Schema::set_short_desc (
    const Glib::ustring & desc )
```

### 8.5.2.22 set\_type()

```
void Gnome::Conf::Schema::set_type (
    ValueType type )
```

## 8.5.3 Friends And Related Symbol Documentation

### 8.5.3.1 wrap()

```
Gnome::Conf::Schema wrap (
    GConfSchema * object,
    bool take_copy = false ) [related]
```

A Glib::wrap() method for this object.

#### Parameters

<i>object</i>	The C instance.
<i>take_copy</i>	False if the result should take ownership of the C instance. True if it should take a new copy or ref.

#### Returns

A C++ instance that wraps this C instance.

## 8.5.4 Member Data Documentation

### 8.5.4.1 gobject\_

```
GConfSchema* Gnome::Conf::Schema::gobject_ [protected]
```

The documentation for this class was generated from the following file:


- gconfmm/schema.h

## 8.6 Gnome::Conf::SetInterface Class Reference

Common Interface for key-value settable objects.

```
#include <gconfmm/setinterface.h>
```

Inheritance diagram for Gnome::Conf::SetInterface:



### Public Member Functions

- virtual void [set](#) (const Glib::ustring &key, const [Value](#) &value)=0
- virtual void [set](#) (const Glib::ustring &key, bool what)=0
- virtual void [set](#) (const Glib::ustring &key, int what)=0
- virtual void [set](#) (const Glib::ustring &key, double what)=0
- virtual void [set](#) (const Glib::ustring &key, const Glib::ustring &what)=0
- virtual void [set](#) (const Glib::ustring &key, const [Schema](#) &what)=0
- void [set](#) (const Glib::ustring &key, const [ValuePair](#) &pair)
- void [set\\_int\\_list](#) (const Glib::ustring &key, const SListHandle\_ValueInt &list)
- void [set\\_bool\\_list](#) (const Glib::ustring &key, const SListHandle\_ValueBool &list)
- void [set\\_float\\_list](#) (const Glib::ustring &key, const SListHandle\_ValueFloat &list)
- void [set\\_string\\_list](#) (const Glib::ustring &key, const SListHandle\_ValueString &list)
- void [set\\_schema\\_list](#) (const Glib::ustring &key, const SListHandle\_ValueSchema &list)

### 8.6.1 Detailed Description

Common Interface for key-value settable objects.

This class defines a common interface for GConfmm objects that implement the [set\(\)](#) methods for configuration keys. It also provides the implementations for the [set\\_\\*\\_list\(\)](#) family of methods.

The only classes that support this interface are [Client](#) and [ChangeSet](#).

The [set\\_\\*\\_list\(\)](#) methods take as a parameter any STL-compatible container that has the appropriate [value\\_type](#).

### 8.6.2 Member Function Documentation

#### 8.6.2.1 [set\(\)](#) [1/7]

```
virtual void Gnome::Conf::SetInterface::set (
    const Glib::ustring & key,
    bool what ) [pure virtual]
```

Implemented in [Gnome::Conf::ChangeSet](#), and [Gnome::Conf::Client](#).

#### 8.6.2.2 set() [2/7]

```
virtual void Gnome::Conf::SetInterface::set (
    const Glib::ustring & key,
    const Glib::ustring & what ) [pure virtual]
```

Implemented in [Gnome::Conf::ChangeSet](#), and [Gnome::Conf::Client](#).

#### 8.6.2.3 set() [3/7]

```
virtual void Gnome::Conf::SetInterface::set (
    const Glib::ustring & key,
    const Schema & what ) [pure virtual]
```

Implemented in [Gnome::Conf::ChangeSet](#), and [Gnome::Conf::Client](#).

#### 8.6.2.4 set() [4/7]

```
virtual void Gnome::Conf::SetInterface::set (
    const Glib::ustring & key,
    const Value & value ) [pure virtual]
```

Implemented in [Gnome::Conf::ChangeSet](#), and [Gnome::Conf::Client](#).

#### 8.6.2.5 set() [5/7]

```
void Gnome::Conf::SetInterface::set (
    const Glib::ustring & key,
    const ValuePair & pair )
```

#### 8.6.2.6 set() [6/7]

```
virtual void Gnome::Conf::SetInterface::set (
    const Glib::ustring & key,
    double what ) [pure virtual]
```

Implemented in [Gnome::Conf::ChangeSet](#), and [Gnome::Conf::Client](#).

#### 8.6.2.7 set() [7/7]

```
virtual void Gnome::Conf::SetInterface::set (
    const Glib::ustring & key,
    int what ) [pure virtual]
```

Implemented in [Gnome::Conf::ChangeSet](#), and [Gnome::Conf::Client](#).



**8.6.2.8 set\_bool\_list()**

```
void Gnome::Conf::SetInterface::set_bool_list (
    const Glib::ustring & key,
    const SListHandle_ValueBool & list )
```

**8.6.2.9 set\_float\_list()**

```
void Gnome::Conf::SetInterface::set_float_list (
    const Glib::ustring & key,
    const SListHandle_ValueFloat & list )
```

**8.6.2.10 set\_int\_list()**

```
void Gnome::Conf::SetInterface::set_int_list (
    const Glib::ustring & key,
    const SListHandle_ValueInt & list )
```

**8.6.2.11 set\_schema\_list()**

```
void Gnome::Conf::SetInterface::set_schema_list (
    const Glib::ustring & key,
    const SListHandle_ValueSchema & list )
```

**8.6.2.12 set\_string\_list()**

```
void Gnome::Conf::SetInterface::set_string_list (
    const Glib::ustring & key,
    const SListHandle_ValueString & list )
```

The documentation for this class was generated from the following file:


- gconfmm/setinterface.h

**8.7 Gnome::Conf::Value Class Reference**

Wrapper for primitive types.

```
#include <gconfmm/value.h>
```

Collaboration diagram for Gnome::Conf::Value:



## Public Member Functions

- [Value](#) (GConfValue \*castitem, bool make\_a\_copy=false)
- [Value](#) (const [Value](#) &src)
- [Value](#) & [operator=](#) (const [Value](#) &src)
- [~Value](#) ()
- GConfValue \* [gobj](#) ()
- const GConfValue \* [gobj](#) () const
- GConfValue \* [gobj\\_copy](#) () const
 

*Provides access to the underlying C instance. The caller is responsible for freeing it. Use when directly setting fields in structs.*
- [Value](#) (ValueType type=VALUE\_INVALID)
 

*Create a [Value](#).*
- void [set](#) (gint val)
 

*Set the integer value of a [Value](#) whose type is VALUE\_INT.*
- void [set](#) (gdouble val)
 

*Set the float value of a [Value](#) whose type is VALUE\_FLOAT.*
- void [set](#) (bool val)
 

*Set the boolean value of a [Value](#) whose type is VALUE\_BOOL.*
- void [set](#) (const [Schema](#) &sc)
 

*Set the [Schema](#) of a [Value](#) whose type is VALUE\_SCHEMA.*
- void [set\\_car](#) (const [Value](#) &car)
 

*Set the car (in a pair, the first element) of a [Value](#) whose type is VALUE\_PAIR.*
- void [set\\_cdr](#) (const [Value](#) &cdr)
 

*Set the cdr (in a pair, the second element) of a [Value](#) whose type is VALUE\_PAIR.*
- void [set](#) (const Glib::ustring &val)
 

*Set the string of a [Value](#) whose type is VALUE\_STRING.*
- void [set\\_list\\_type](#) (ValueType type)
 

*Sets the type of the elements of a [Value](#) with type VALUE\_LIST.*
- void [set\\_int\\_list](#) (const SListHandle\_ValueInt &list)
 

*Sets the [Value](#) to contain a list of integers.*
- void [set\\_bool\\_list](#) (const SListHandle\_ValueBool &list)
 

*Sets the [Value](#) to contain a list of booleans.*
- void [set\\_float\\_list](#) (const SListHandle\_ValueFloat &list)
 

*Sets the [Value](#) to contain a list of doubles.*
- void [set\\_string\\_list](#) (const SListHandle\_ValueString &list)
 

*Sets the [Value](#) to contain a list of strings.*
- void [set\\_schema\\_list](#) (const SListHandle\_ValueSchema &list)
 

*Sets the [Value](#) to contain a list of [Schema](#).*
- ValueType [get\\_type](#) () const
 

*Get the type of the [Value](#).*
- ValueType [get\\_list\\_type](#) () const
 

*Get the type of the list elements of the [Value](#).*
- int [get\\_int](#) () const
 

*Get the integer that the [Value](#) contains.*
- bool [get\\_bool](#) () const
 

*Get the boolean that the [Value](#) contains.*
- double [get\\_float](#) () const
 

*Get the double that the [Value](#) contains.*
- Glib::ustring [get\\_string](#) () const
 

*Get the string that the [Value](#) contains.*
- [Schema](#) [get\\_schema](#) () const

- Get a copy of the [Schema](#) of the value.

  - [Value get\\_car](#) () const
 

Get a copy of the car of a [VALUE\\_PAIR Value](#).
  - [Value get\\_cdr](#) () const
 

Get a copy of the cdr of a [VALUE\\_PAIR Value](#).
  - [SListHandle\\_ValueFloat get\\_float\\_list](#) () const
 

Gets a list of doubles from the [Value](#).
  - [SListHandle\\_ValueInt get\\_int\\_list](#) () const
 

Retrieves the list of integers from the [Value](#).
  - [SListHandle\\_ValueBool get\\_bool\\_list](#) () const
 

Retrieves the list of booleans from the [Value](#).
  - [SListHandle\\_ValueString get\\_string\\_list](#) () const
 

Retrieves the list of strings from the [Value](#).
  - [SListHandle\\_ValueSchema get\\_schema\\_list](#) () const
 

Retrieves the list of Schemas from the [Value](#).
  - [Glib::ustring to\\_string](#) () const
 

Convert the [Value](#) to a string.

### Protected Attributes

- [GConfValue \\* gobject\\_](#)

### Related Symbols

(Note that these are not member symbols.)

- [Gnome::Conf::Value wrap](#) ([GConfValue \\*object](#), [bool take\\_copy=false](#))
 

A [Glib::wrap\(\)](#) method for this object.

## 8.7.1 Detailed Description

Wrapper for primitive types.

This class wraps the primitive types that are passed to and from instances of [Gnome::Conf::Client](#). It has an associated [ValueType](#), which is specified at creation time, but can be changed with assignment. If the type is [VALUE\\_INVALID](#) then the effect of the set and get methods is undefined. Using a default-constructed [Value](#) without using any of the set methods produces undefined behaviour.

Compound Values of type [VALUE\\_PAIR](#) and [VALUE\\_LIST](#) can only have elements whose types are neither [VALUE\\_PAIR](#) or [VALUE\\_LIST](#) - they can only have primitive types.

The [Value](#) class has copy-by-value semantics - all arguments to the set methods are copied.

Note that while the type is named [VALUE\\_FLOAT](#), the accessors for floating-point values use `double`, not `float`, to preserve accuracy.

## 8.7.2 Constructor & Destructor Documentation

### 8.7.2.1 Value() [1/3]

```
Gnome::Conf::Value::Value (
    GConfValue * castitem,
    bool make_a_copy = false ) [explicit]
```

### 8.7.2.2 Value() [2/3]

```
Gnome::Conf::Value::Value (
    const Value & src )
```

### 8.7.2.3 ~Value()

```
Gnome::Conf::Value::~~Value ( )
```

### 8.7.2.4 Value() [3/3]

```
Gnome::Conf::Value::Value (
    ValueType type = VALUE_INVALID )
```

Create a [Value](#).

You should call a `set()` method before using the [Value](#).

#### Parameters

<i>type</i>	The type of the produced value.
-------------	---------------------------------

## 8.7.3 Member Function Documentation

### 8.7.3.1 get\_bool()

```
bool Gnome::Conf::Value::get_bool ( ) const
```

Get the boolean that the [Value](#) contains.

### 8.7.3.2 get\_bool\_list()

```
SListHandle_ValueBool Gnome::Conf::Value::get_bool_list ( ) const
```

Retrieves the list of booleans from the [Value](#).

#### See also

[get\\_float\\_list](#)

### 8.7.3.3 get\_car()

`Value Gnome::Conf::Value::get_car ( ) const`

Get a copy of the car of a VALUE\_PAIR [Value](#).

### 8.7.3.4 get\_cdr()

`Value Gnome::Conf::Value::get_cdr ( ) const`

Get a copy of the cdr of a VALUE\_PAIR [Value](#).

### 8.7.3.5 get\_float()

`double Gnome::Conf::Value::get_float ( ) const`

Get the double that the [Value](#) contains.

### 8.7.3.6 get\_float\_list()

`SListHandle_ValueFloat Gnome::Conf::Value::get_float_list ( ) const`

Gets a list of doubles from the [Value](#).

Typical usage is

```
std::vector<double> foo = value.get_float_list();
```

.

#### Returns

: an STL-compatible container with doubles as its value type. Assign to an **std::vector**, list or deque for proper use.

### 8.7.3.7 get\_int()

`int Gnome::Conf::Value::get_int ( ) const`

Get the integer that the [Value](#) contains.

### 8.7.3.8 get\_int\_list()

`SListHandle_ValueInt Gnome::Conf::Value::get_int_list ( ) const`

Retrieves the list of integers from the [Value](#).

#### See also

[get\\_float\\_list](#)

#### 8.7.3.9 get\_list\_type()

`ValueType` Gnome::Conf::Value::get\_list\_type ( ) const

Get the type of the list elements of the [Value](#).

Do not call this method on non-list Values.

##### Returns

the type of the list elements.

#### 8.7.3.10 get\_schema()

`Schema` Gnome::Conf::Value::get\_schema ( ) const

Get a copy of the [Schema](#) of the value.

#### 8.7.3.11 get\_schema\_list()

`SListHandle_ValueSchema` Gnome::Conf::Value::get\_schema\_list ( ) const

Retrieves the list of Schemas from the [Value](#).

@See [get\\_float\\_list](#)

#### 8.7.3.12 get\_string()

`Glib::ustring` Gnome::Conf::Value::get\_string ( ) const

Get the string that the [Value](#) contains.

#### 8.7.3.13 get\_string\_list()

`SListHandle_ValueString` Gnome::Conf::Value::get\_string\_list ( ) const

Retrieves the list of strings from the [Value](#).

##### See also

[get\\_float\\_list](#)

#### 8.7.3.14 get\_type()

`ValueType` Gnome::Conf::Value::get\_type ( ) const

Get the type of the [Value](#).

##### Returns

the type of the [Value](#)

**8.7.3.15 gobj()** [1/2]

```
GConfValue * Gnome::Conf::Value::gobj ( ) [inline]
```

**8.7.3.16 gobj()** [2/2]

```
const GConfValue * Gnome::Conf::Value::gobj ( ) const [inline]
```

**8.7.3.17 gobj\_copy()**

```
GConfValue * Gnome::Conf::Value::gobj_copy ( ) const
```

Provides access to the underlying C instance. The caller is responsible for freeing it. Use when directly setting fields in structs.

**8.7.3.18 operator=()**

```
Value & Gnome::Conf::Value::operator= (
    const Value & src )
```

**8.7.3.19 set()** [1/5]

```
void Gnome::Conf::Value::set (
    bool val )
```

Set the boolean value of a [Value](#) whose type is VALUE\_BOOL.

**8.7.3.20 set()** [2/5]

```
void Gnome::Conf::Value::set (
    const Glib::ustring & val )
```

Set the string of a [Value](#) whose type is VALUE\_STRING.

**8.7.3.21 set()** [3/5]

```
void Gnome::Conf::Value::set (
    const Schema & sc )
```

Set the [Schema](#) of a [Value](#) whose type is VALUE\_SCHEMA.

**8.7.3.22 set()** [4/5]

```
void Gnome::Conf::Value::set (
    gdouble val )
```

Set the float value of a [Value](#) whose type is VALUE\_FLOAT.

## Parameters

<code>val</code>	the double this <a href="#">Value</a> will be se to.
------------------	--

**8.7.3.23 set()** [5/5]

```
void Gnome::Conf::Value::set (
    gint val )
```

Set the integer value of a [Value](#) whose type is VALUE\_INT.

**8.7.3.24 set\_bool\_list()**

```
void Gnome::Conf::Value::set_bool_list (
    const SListHandle_ValueBool & list )
```

Sets the [Value](#) to contain a list of bools.

See also

[set\\_int\\_list](#)

**8.7.3.25 set\_car()**

```
void Gnome::Conf::Value::set_car (
    const Value & car )
```

Set the car (in a pair, the first element) of a [Value](#) whose type is VALUE\_PAIR.

**8.7.3.26 set\_cdr()**

```
void Gnome::Conf::Value::set_cdr (
    const Value & cdr )
```

Set the cdr (in a pair, the second element) of a [Value](#) whose type is VALUE\_PAIR.

**8.7.3.27 set\_float\_list()**

```
void Gnome::Conf::Value::set_float_list (
    const SListHandle_ValueFloat & list )
```

Sets the [Value](#) to contain a list of doubles.

See also

[set\\_int\\_list](#)

**8.7.3.28 set\_int\_list()**

```
void Gnome::Conf::Value::set_int_list (
    const SListHandle_ValueInt & list )
```

Sets the [Value](#) to contain a list of integers.

`set_list_type(VALUE_INT)` must have been called prior this call.



## Parameters

<i>list</i>	an STL-compatible container whose value_type is int
-------------	---

**8.7.3.29 set\_list\_type()**

```
void Gnome::Conf::Value::set_list_type (
    ValueType type )
```

Sets the type of the elements of a [Value](#) with type VALUE\_LIST.

**8.7.3.30 set\_schema\_list()**

```
void Gnome::Conf::Value::set_schema_list (
    const SListHandle_ValueSchema & list )
```

Sets the [Value](#) to contain a list of [Schema](#).

See also

[set\\_int\\_list](#)

**8.7.3.31 set\_string\_list()**

```
void Gnome::Conf::Value::set_string_list (
    const SListHandle_ValueString & list )
```

Sets the [Value](#) to contain a list of strings.

See also

[set\\_int\\_list](#)

**8.7.3.32 to\_string()**

```
Glib::ustring Gnome::Conf::Value::to_string ( ) const
```

Convert the [Value](#) to a string.

The string is not machine-parseable. Do not depend on the format of the string.

**8.7.4 Friends And Related Symbol Documentation****8.7.4.1 wrap()**

```
Gnome::Conf::Value wrap (
    GConfValue * object,
    bool take_copy = false ) [related]
```

A Glib::wrap() method for this object.

**Parameters**

<i>object</i>	The C instance.
<i>take_copy</i>	False if the result should take ownership of the C instance. True if it should take a new copy or ref.

**Returns**

A C++ instance that wraps this C instance.

## 8.7.5 Member Data Documentation

### 8.7.5.1 gobject\_

GConfValue\* Gnome::Conf::Value::gobject\_ [protected]

The documentation for this class was generated from the following file:

- gconfmm/value.h

# Index

- ~ChangeSet
  - Gnome::Conf::ChangeSet, [17](#)
- ~Client
  - Gnome::Conf::Client, [24](#)
- ~Entry
  - Gnome::Conf::Entry, [43](#)
- ~Schema
  - Gnome::Conf::Schema, [49](#)
- ~Value
  - Gnome::Conf::Value, [58](#)
- add\_dir
  - Gnome::Conf::Client, [24](#)
- all\_dirs
  - Gnome::Conf::Client, [25](#)
- all\_entries
  - Gnome::Conf::Client, [25](#)
- BAD\_ADDRESS
  - Gnome::Conf::Error, [47](#)
- Callback
  - Gnome::Conf, [14](#)
- change\_set\_commit
  - Gnome::Conf::Client, [25](#)
- change\_set\_from\_current
  - Gnome::Conf::Client, [26](#)
- change\_set\_reverse
  - Gnome::Conf::Client, [27](#)
- ChangeSet
  - Gnome::Conf::ChangeSet, [17](#)
- clear
  - Gnome::Conf::ChangeSet, [17](#)
- clear\_cache
  - Gnome::Conf::Client, [27](#)
- CLIENT\_HANDLE\_ALL
  - gconfmm Enums and Flags, [11](#)
- CLIENT\_HANDLE\_NONE
  - gconfmm Enums and Flags, [11](#)
- CLIENT\_HANDLE\_UNRETURNED
  - gconfmm Enums and Flags, [11](#)
- CLIENT\_PRELOAD\_NONE
  - gconfmm Enums and Flags, [12](#)
- CLIENT\_PRELOAD\_ONELEVEL
  - gconfmm Enums and Flags, [12](#)
- CLIENT\_PRELOAD\_RECURSIVE
  - gconfmm Enums and Flags, [12](#)
- ClientErrorHandlingMode
  - gconfmm Enums and Flags, [11](#)
- ClientPreloadType
- gconfmm Enums and Flags, [12](#)
- Code
  - Gnome::Conf::Error, [46](#)
- code
  - Gnome::Conf::Error, [47](#)
- CORRUPT
  - Gnome::Conf::Error, [47](#)
- dir\_exists
  - Gnome::Conf::Client, [27](#)
- Entry
  - Gnome::Conf::Entry, [42](#), [43](#)
- Error
  - Gnome::Conf::Error, [47](#)
- error
  - Gnome::Conf::Client, [28](#)
- exists
  - Gnome::Conf::ChangeSet, [17](#)
- for\_each
  - Gnome::Conf::ChangeSet, [18](#)
- ForeachSlot
  - Gnome::Conf::ChangeSet, [17](#)
- gconfmm Enums and Flags, [11](#)
  - CLIENT\_HANDLE\_ALL, [11](#)
  - CLIENT\_HANDLE\_NONE, [11](#)
  - CLIENT\_HANDLE\_UNRETURNED, [11](#)
  - CLIENT\_PRELOAD\_NONE, [12](#)
  - CLIENT\_PRELOAD\_ONELEVEL, [12](#)
  - CLIENT\_PRELOAD\_RECURSIVE, [12](#)
  - ClientErrorHandlingMode, [11](#)
  - ClientPreloadType, [12](#)
  - UNSET\_INCLUDING\_SCHEMA\_NAMES, [12](#)
  - UnsetFlags, [12](#)
  - VALUE\_BOOL, [12](#)
  - VALUE\_FLOAT, [12](#)
  - VALUE\_INT, [12](#)
  - VALUE\_INVALID, [12](#)
  - VALUE\_LIST, [12](#)
  - VALUE\_PAIR, [12](#)
  - VALUE\_SCHEMA, [12](#)
  - VALUE\_STRING, [12](#)
  - ValueType, [12](#)
- gconfmm Reference Manual, [1](#)
- get
  - Gnome::Conf::Client, [28](#)
- get\_bool
  - Gnome::Conf::Client, [28](#)

- Gnome::Conf::Value, 58
- get\_bool\_list
  - Gnome::Conf::Client, 28
  - Gnome::Conf::Value, 58
- get\_car
  - Gnome::Conf::Value, 58
- get\_car\_type
  - Gnome::Conf::Schema, 49
- get\_cdr
  - Gnome::Conf::Value, 59
- get\_cdr\_type
  - Gnome::Conf::Schema, 49
- get\_client\_for\_engine
  - Gnome::Conf::Client, 28
- get\_default\_client
  - Gnome::Conf::Client, 28
- get\_default\_from\_schema
  - Gnome::Conf::Client, 29
- get\_default\_value
  - Gnome::Conf::Schema, 49
- get\_entry
  - Gnome::Conf::Client, 29, 30
- get\_float
  - Gnome::Conf::Client, 30
  - Gnome::Conf::Value, 59
- get\_float\_list
  - Gnome::Conf::Client, 30
  - Gnome::Conf::Value, 59
- get\_int
  - Gnome::Conf::Client, 31
  - Gnome::Conf::Value, 59
- get\_int\_list
  - Gnome::Conf::Client, 31
  - Gnome::Conf::Value, 59
- get\_is\_default
  - Gnome::Conf::Entry, 43
- get\_is\_writable
  - Gnome::Conf::Entry, 43
- get\_key
  - Gnome::Conf::Entry, 43
- get\_list\_type
  - Gnome::Conf::Schema, 50
  - Gnome::Conf::Value, 59
- get\_locale
  - Gnome::Conf::Schema, 50
- get\_long\_desc
  - Gnome::Conf::Schema, 50
- get\_owner
  - Gnome::Conf::Schema, 50
- get\_pair
  - Gnome::Conf::Client, 31
- get\_schema
  - Gnome::Conf::Client, 32
  - Gnome::Conf::Value, 60
- get\_schema\_list
  - Gnome::Conf::Client, 32
  - Gnome::Conf::Value, 60
- get\_schema\_name
  - Gnome::Conf::Entry, 43
- get\_short\_desc
  - Gnome::Conf::Schema, 50
- get\_string
  - Gnome::Conf::Client, 32
  - Gnome::Conf::Value, 60
- get\_string\_list
  - Gnome::Conf::Client, 32
  - Gnome::Conf::Value, 60
- get\_type
  - Gnome::Conf::Schema, 50
  - Gnome::Conf::Value, 60
- get\_value
  - Gnome::Conf::Entry, 43
- get\_without\_default
  - Gnome::Conf::Client, 32
- Glib, 13
- Gnome, 13
- Gnome::Conf, 13
  - Callback, 14
  - init, 14
  - ValuePair, 14
  - ValueTypePair, 14
- Gnome::Conf::ChangeSet, 15
  - ~ChangeSet, 17
  - ChangeSet, 17
  - clear, 17
  - exists, 17
  - for\_each, 18
  - ForeachSlot, 17
  - gobj, 18
  - gobj\_copy, 18
  - gobject\_, 20
  - operator=, 18
  - remove, 18
  - set, 18, 19
  - size, 19
  - unset, 20
- Gnome::Conf::Client, 20
  - ~Client, 24
  - add\_dir, 24
  - all\_dirs, 25
  - all\_entries, 25
  - change\_set\_commit, 25
  - change\_set\_from\_current, 26
  - change\_set\_reverse, 27
  - clear\_cache, 27
  - dir\_exists, 27
  - error, 28
  - get, 28
  - get\_bool, 28
  - get\_bool\_list, 28
  - get\_client\_for\_engine, 28
  - get\_default\_client, 28
  - get\_default\_from\_schema, 29
  - get\_entry, 29, 30
  - get\_float, 30
  - get\_float\_list, 30

- get\_int, 31
- get\_int\_list, 31
- get\_pair, 31
- get\_schema, 32
- get\_schema\_list, 32
- get\_string, 32
- get\_string\_list, 32
- get\_without\_default, 32
- gobj, 33
- gobj\_copy, 33
- key\_is\_writable, 33
- notify, 34
- notify\_add, 34
- notify\_remove, 34
- on\_error, 35
- on\_unreturned\_error, 35
- on\_value\_changed, 35
- preload, 35
- recursive\_unset, 35
- remove\_dir, 36
- set, 36–38
- set\_bool\_list, 38
- set\_error\_handling, 39
- set\_float\_list, 39
- set\_int\_list, 39
- set\_schema\_list, 39
- set\_string\_list, 39
- signal\_error, 39
- signal\_value\_changed, 39
- SListHandleBools, 24
- SListHandleFloats, 24
- SListHandleInts, 24
- suggest\_sync, 40
- unset, 40
- value\_changed, 40
- wrap, 41
- Gnome::Conf::Entry, 41
  - ~Entry, 43
  - Entry, 42, 43
  - get\_is\_default, 43
  - get\_is\_writable, 43
  - get\_key, 43
  - get\_schema\_name, 43
  - get\_value, 43
  - gobj, 44
  - gobj\_copy, 44
  - gobject\_, 45
  - operator=, 44
  - set\_is\_default, 44
  - set\_is\_writable, 44
  - set\_schema\_name, 44
  - set\_value, 45
- Gnome::Conf::Error, 45
  - BAD\_ADDRESS, 47
  - Code, 46
  - code, 47
  - CORRUPT, 47
  - Error, 47
  - IN\_SHUTDOWN, 47
  - IS\_DIR, 47
  - IS\_KEY, 47
  - LOCAL\_ENGINE, 47
  - LOCK\_FAILED, 47
  - NO\_PERMISSION, 47
  - NO\_SERVER, 47
  - NO\_WRITABLE\_DATABASE, 47
  - OAF\_ERROR, 47
  - OVERRIDDEN, 47
  - PARSE\_ERROR, 47
  - SUCCESS, 47
  - TYPE\_MISMATCH, 47
- Gnome::Conf::Schema, 48
  - ~Schema, 49
  - get\_car\_type, 49
  - get\_cdr\_type, 49
  - get\_default\_value, 49
  - get\_list\_type, 50
  - get\_locale, 50
  - get\_long\_desc, 50
  - get\_owner, 50
  - get\_short\_desc, 50
  - get\_type, 50
  - gobj, 50
  - gobj\_copy, 50
  - gobject\_, 52
  - operator=, 50
  - Schema, 49
  - set\_car\_type, 51
  - set\_cdr\_type, 51
  - set\_default\_value, 51
  - set\_list\_type, 51
  - set\_locale, 51
  - set\_long\_desc, 51
  - set\_owner, 51
  - set\_short\_desc, 51
  - set\_type, 51
  - wrap, 52
- Gnome::Conf::SetInterface, 52
  - set, 53, 54
  - set\_bool\_list, 54
  - set\_float\_list, 55
  - set\_int\_list, 55
  - set\_schema\_list, 55
  - set\_string\_list, 55
- Gnome::Conf::Value, 55
  - ~Value, 58
  - get\_bool, 58
  - get\_bool\_list, 58
  - get\_car, 58
  - get\_cdr, 59
  - get\_float, 59
  - get\_float\_list, 59
  - get\_int, 59
  - get\_int\_list, 59
  - get\_list\_type, 59
  - get\_schema, 60

- get\_schema\_list, 60
- get\_string, 60
- get\_string\_list, 60
- get\_type, 60
- gobj, 60, 61
- gobj\_copy, 61
- gobject\_, 64
- operator=, 61
- set, 61, 62
- set\_bool\_list, 62
- set\_car, 62
- set\_cdr, 62
- set\_float\_list, 62
- set\_int\_list, 62
- set\_list\_type, 63
- set\_schema\_list, 63
- set\_string\_list, 63
- to\_string, 63
- Value, 58
- wrap, 63
- gobj
  - Gnome::Conf::ChangeSet, 18
  - Gnome::Conf::Client, 33
  - Gnome::Conf::Entry, 44
  - Gnome::Conf::Schema, 50
  - Gnome::Conf::Value, 60, 61
- gobj\_copy
  - Gnome::Conf::ChangeSet, 18
  - Gnome::Conf::Client, 33
  - Gnome::Conf::Entry, 44
  - Gnome::Conf::Schema, 50
  - Gnome::Conf::Value, 61
- gobject\_
  - Gnome::Conf::ChangeSet, 20
  - Gnome::Conf::Entry, 45
  - Gnome::Conf::Schema, 52
  - Gnome::Conf::Value, 64
- IN\_SHUTDOWN
  - Gnome::Conf::Error, 47
- init
  - Gnome::Conf, 14
- IS\_DIR
  - Gnome::Conf::Error, 47
- IS\_KEY
  - Gnome::Conf::Error, 47
- key\_is\_writable
  - Gnome::Conf::Client, 33
- LOCAL\_ENGINE
  - Gnome::Conf::Error, 47
- LOCK\_FAILED
  - Gnome::Conf::Error, 47
- NO\_PERMISSION
  - Gnome::Conf::Error, 47
- NO\_SERVER
  - Gnome::Conf::Error, 47
- NO\_WRITABLE\_DATABASE
  - Gnome::Conf::Error, 47
- notify
  - Gnome::Conf::Client, 34
- notify\_add
  - Gnome::Conf::Client, 34
- notify\_remove
  - Gnome::Conf::Client, 34
- OAF\_ERROR
  - Gnome::Conf::Error, 47
- on\_error
  - Gnome::Conf::Client, 35
- on\_unreturned\_error
  - Gnome::Conf::Client, 35
- on\_value\_changed
  - Gnome::Conf::Client, 35
- operator=
  - Gnome::Conf::ChangeSet, 18
  - Gnome::Conf::Entry, 44
  - Gnome::Conf::Schema, 50
  - Gnome::Conf::Value, 61
- OVERRIDDEN
  - Gnome::Conf::Error, 47
- PARSE\_ERROR
  - Gnome::Conf::Error, 47
- preload
  - Gnome::Conf::Client, 35
- recursive\_unset
  - Gnome::Conf::Client, 35
- remove
  - Gnome::Conf::ChangeSet, 18
- remove\_dir
  - Gnome::Conf::Client, 36
- Schema
  - Gnome::Conf::Schema, 49
- set
  - Gnome::Conf::ChangeSet, 18, 19
  - Gnome::Conf::Client, 36–38
  - Gnome::Conf::SetInterface, 53, 54
  - Gnome::Conf::Value, 61, 62
- set\_bool\_list
  - Gnome::Conf::Client, 38
  - Gnome::Conf::SetInterface, 54
  - Gnome::Conf::Value, 62
- set\_car
  - Gnome::Conf::Value, 62
- set\_car\_type
  - Gnome::Conf::Schema, 51
- set\_cdr
  - Gnome::Conf::Value, 62
- set\_cdr\_type
  - Gnome::Conf::Schema, 51
- set\_default\_value
  - Gnome::Conf::Schema, 51
- set\_error\_handling

- Gnome::Conf::Client, 39
- set\_float\_list
  - Gnome::Conf::Client, 39
  - Gnome::Conf::SetInterface, 55
  - Gnome::Conf::Value, 62
- set\_int\_list
  - Gnome::Conf::Client, 39
  - Gnome::Conf::SetInterface, 55
  - Gnome::Conf::Value, 62
- set\_is\_default
  - Gnome::Conf::Entry, 44
- set\_is\_writable
  - Gnome::Conf::Entry, 44
- set\_list\_type
  - Gnome::Conf::Schema, 51
  - Gnome::Conf::Value, 63
- set\_locale
  - Gnome::Conf::Schema, 51
- set\_long\_desc
  - Gnome::Conf::Schema, 51
- set\_owner
  - Gnome::Conf::Schema, 51
- set\_schema\_list
  - Gnome::Conf::Client, 39
  - Gnome::Conf::SetInterface, 55
  - Gnome::Conf::Value, 63
- set\_schema\_name
  - Gnome::Conf::Entry, 44
- set\_short\_desc
  - Gnome::Conf::Schema, 51
- set\_string\_list
  - Gnome::Conf::Client, 39
  - Gnome::Conf::SetInterface, 55
  - Gnome::Conf::Value, 63
- set\_type
  - Gnome::Conf::Schema, 51
- set\_value
  - Gnome::Conf::Entry, 45
- signal\_error
  - Gnome::Conf::Client, 39
- signal\_value\_changed
  - Gnome::Conf::Client, 39
- size
  - Gnome::Conf::ChangeSet, 19
- SListHandleBools
  - Gnome::Conf::Client, 24
- SListHandleFloats
  - Gnome::Conf::Client, 24
- SListHandleInts
  - Gnome::Conf::Client, 24
- SUCCESS
  - Gnome::Conf::Error, 47
- suggest\_sync
  - Gnome::Conf::Client, 40
- to\_string
  - Gnome::Conf::Value, 63
- TYPE\_MISMATCH
  - Gnome::Conf::Error, 47
- unset
  - Gnome::Conf::ChangeSet, 20
  - Gnome::Conf::Client, 40
- UNSET\_INCLUDING\_SCHEMA\_NAMES
  - gconfmm Enums and Flags, 12
- UnsetFlags
  - gconfmm Enums and Flags, 12
- Value
  - Gnome::Conf::Value, 58
- VALUE\_BOOL
  - gconfmm Enums and Flags, 12
- value\_changed
  - Gnome::Conf::Client, 40
- VALUE\_FLOAT
  - gconfmm Enums and Flags, 12
- VALUE\_INT
  - gconfmm Enums and Flags, 12
- VALUE\_INVALID
  - gconfmm Enums and Flags, 12
- VALUE\_LIST
  - gconfmm Enums and Flags, 12
- VALUE\_PAIR
  - gconfmm Enums and Flags, 12
- VALUE\_SCHEMA
  - gconfmm Enums and Flags, 12
- VALUE\_STRING
  - gconfmm Enums and Flags, 12
- ValuePair
  - Gnome::Conf, 14
- ValueType
  - gconfmm Enums and Flags, 12
- ValueTypePair
  - Gnome::Conf, 14
- wrap
  - Gnome::Conf::Client, 41
  - Gnome::Conf::Schema, 52
  - Gnome::Conf::Value, 63